

**RCX340** 

Programming Manual

EGR9148110 E135

# Introduction

Our sincere thanks for your purchase of this YAMAHA RCX340 robot controller.

This manual describes robot program commands and related information for using YAMAHA RCX340 robot controllers. Be sure to read this manual carefully as well as related manuals and comply with their instructions for using the YAMAHA robot controllers safely and correctly. For details on how to operate YAMAHA robot controllers, refer to the separate controller user's manual that comes with the YAMAHA robot controller.

Applicable controllers: RCX340

# Safety precautions

#### Be sure to read before using

Before using the YAMAHA robot controller, be sure to read this manual and related manuals, and follow their instructions to use the robot controller safely and correctly.

Warning and caution items listed in this manual relate to YAMAHA robot controllers.

When this robot controller is used in a robot controller system, please take appropriate safety measures as required by the user's individual system.

This manual classifies safety caution items and operating points into the following levels, along with symbols for signal words "CAUTION" and "NOTE".



# (1) CAUTION

"CAUTION" indicates a potentially hazardous situation which, if not avoided, could result in minor or moderate injury or damage to the equipment or software.



Primarily explains function differences, etc., between software versions.



Explains robot operation procedures in a simple and clear manner.

Note that the items classified into "CAUTION" might result in serious injury depending on the situation or environmental conditions. So always comply with CAUTION instructions since these are essential to maintain safety.

Keep this manual carefully so that the operator can refer to it when needed. Also make sure that this manual reaches the end user.

#### ■ System design precautions



# LAUTION

When the program execution stops before it is complete, the program re-executes the command that has stopped. Keep this point in mind when re-executing the program, for example, when using an arch motion with the MOVE command, a relative movement command such as the MOVEI or DRIVEI command, or a communication command such as the SEND command.

Chapter 1 Writing Programs	
1 The YAMAHA Robot Language	1-1
2 Characters	1-1
3 Program Basics	1-1
4 Program Names	1-2
5 Identifiers	1-4
6 LABEL Statement	1-4
7 Comment	1-5
8 Command Statement Format	1-5
Chapter 2 Constants	
1 Outline	2-1
2 Numeric constants	2-1
2.1 Integer constants	2-1
2.2 Real constants	2-1
3 Character constants	2-2
Chapter 3 Variables	
1 Outline	3-1
2 User Variables & System Variables	3-2
2.1 User Variables	3-2
2.2 System Variables	3-2
3 Variable Names	3-3
3.1 Dynamic Variable Names	3-3
3.2 Static Variable Names	3-3
4 Variable Types	3-4
4.1 Numeric variables	3-4
4.2 Character variables	3-4
5 Array variables	3-5

6	Value Assignments	3-5
7	Type Conversions	3-6
8	Value Pass-Along & Reference Pass-Along	3-6
9	System Variables	3-7
9.	0.1 Point data variable	3-7
9.	0.2 Shift coordinate variable	3-8
9.	9.3 Parallel input variable	3-8
9.	0.4 Parallel output variable	3-9
9.	9.5 Internal output variable	3-10
9.	9.6 Arm lock output variable	3-11
9.	7.7 Timer output variable	3-12
9.	9.8 Serial input variable	3-13
9.	9.9 Serial output variable	3-14
9.	0.10 Serial word input	3-15
9.	0.11 Serial double word input	3-15
9.	0.12 Serial word output	3-16
9.	0.13 Serial double word output	3-16
10	Bit Settings	3-17
11	Valid range of variables	3-18
1	1.1 Valid range of dynamic variables	3-18
	<ul><li>1.1 Valid range of dynamic variables</li><li>1.2 Valid range of static variables</li></ul>	3-18 3-18
11		
1°	1.2 Valid range of static variables	3-18
12	<ul><li>1.2 Valid range of static variables</li><li>1.3 Valid range of dynamic array variables</li></ul>	3-18 3-18
11 11 12	<ul><li>1.2 Valid range of static variables</li><li>1.3 Valid range of dynamic array variables</li><li>Clearing variables</li></ul>	3-18 3-18 <b>3-19</b>
12 12 12	<ul> <li>1.2 Valid range of static variables</li> <li>1.3 Valid range of dynamic array variables</li> <li>Clearing variables</li> <li>2.1 Clearing dynamic variables</li> </ul>	3-18 3-19 3-19
12 12 12 12 Ch	<ul> <li>1.2 Valid range of static variables</li> <li>1.3 Valid range of dynamic array variables</li> <li>Clearing variables</li> <li>2.1 Clearing dynamic variables</li> <li>2.2 Clearing static variables</li> </ul>	3-18 3-19 3-19
12 12 12 12 Ch	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations	3-18 3-19 3-19 3-19
12 12 12 Ch 1	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations  Arithmetic operations	3-18 3-19 3-19 3-19
11 12 12 12 12 Ch 1	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations  Arithmetic operations  1 Arithmetic operators	3-18 3-19 3-19 3-19 4-1
11 12 12 12 Chr 1 1. 1. 1. 1.	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations  Arithmetic operations  1 Arithmetic operators 2 Relational operators	3-18 3-19 3-19 3-19 4-1 4-1
11 12 12 12 Ch 1 1. 1. 1. 1. 1.	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations  Arithmetic operations  1 Arithmetic operators 2 Relational operators 3 Logic operations	3-18 3-19 3-19 3-19 4-1 4-1 4-1 4-2
11 12 12 12 12 12 12 1. 1. 1. 1. 1.	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations  Arithmetic operations  1 Arithmetic operators 2 Relational operators 3 Logic operations 4 Priority of arithmetic operation	3-18 3-19 3-19 3-19 4-1 4-1 4-1 4-2 4-3
11 12 12 12 12 12 12 1. 1. 1. 1. 1.	1.2 Valid range of static variables 1.3 Valid range of dynamic array variables  Clearing variables 2.1 Clearing dynamic variables 2.2 Clearing static variables  hapter 4 Expressions and Operations  Arithmetic operations  1 Arithmetic operators 2 Relational operators 3 Logic operations 4 Priority of arithmetic operation 5 Data format conversion  Character string operations	3-18 3-19 3-19 3-19 4-1 4-1 4-1 4-2 4-3 4-3

3	Point data format		4-5
4	DI/DO conditional expression	ons	4-6
CI	napter 5 Multiple Robo	t Control	
1	Overview		5-1
2	Command list with a robot	specified	5-2
C	napter 6 Multi-tasking		
1	Outline		6-1
2	Task definition		6-1
3	Task status and transition		6-2
3	.1 Starting tasks		6-2
3	.2 Task scheduling		6-3
3	.3 Condition wait in task		6-4
3	.4 Suspending tasks (SUSPEND	0)	6-5
3	.5 Restarting tasks (RESTART)		6-5
3	.6 Deleting tasks		6-6
3	.7 Stopping tasks		6-7
4	Multi-task program exampl	е	6-8
5	Sharing the data		6-8
6	Cautionary Items		6-9
CI	napter 7 Robot Langua	ge Lists	
Н	ow to read the robot languag	e table	7-1
Co	ommand list in alphabetic or	der	7-2
Fu	nction Specific		7-6
Fu	nctions: in alphabetic order		7-11
Fu	nctions: operation-specific		7-13
1	ABS	Acquires absolute values	7-15
2	ABSRPOS	Acquires a machine reference	7-16
3	ACCEL	Specifies/acquires the acceleration coefficient parameter	7-17

4	ARCHP1 / ARCHP2	Specifies/acquires the acceleration coefficient parameter	7-18
5	ARMCND	Arm status acquisition	7-20
6	ARMSEL	Sets/acquires the current hand system selection.	7-21
7	ARMTYP	Sets/acquires the hand system selection during program reset.	7-22
8	ASPEED	Sets/acquires the AUTO movement speed of a specified robot.	7-23
9	ATN / ATN2	Acquires the arctangent of the specified value	7-24
10	AXWGHT	Sets/acquires the axis tip weight	7-25
11	CALL	Calls a sub-procedure	7-26
12	CHANGE	Switches the hand	7-27
13	CHGPRI	Changes the priority ranking of a specified task	7-28
14	CHR\$	Acquires a character with the specified character code	7-29
15	COS	Acquires the cosine value of a specified value	7-30
16	CURTQST	Acquires the current torque against the rated torque of a specified axis	7-31
17	CURTRQ	Acquires the current torque value of the specified axis	7-32
18	CUT	Terminates another task which is currently being executed	7-33
19	DATE\$	Acquires the date	7-34
20	DECEL	Specifies/acquires the deceleration rate parameter	7-35
21	DEF FN	Defines functions which can be used by the user	7-36
22	DEGRAD	Angle conversion (angle $\rightarrow$ radian)	7-37
23	DELAY	Program execution waits for a specified period of time	7-38
24	DI	Acquires the input status from the parallel port	7-39
25	DIM	Declares array variable	7-40
26	DIST	Acquires the distance between 2 specified points	7-41
27	DO	Outputs to parallel port	7-42
28	DRIVE	Executes absolute movement of specified axes	7-43
29	DRIVEI	Moves the specified robot axes in a relative manner	7-49
30	END SELECT	Ends the SELECT CASE statement	7-54
31	END SUB	Ends the sub-procedure definition	7-55
32	ERR / ERL	Acquires the error code / error line No	7-56
33	EXIT FOR	Terminates the FOR to NEXT statement loop	7-57
34	EXIT SUB	Terminates the sub-procedure defined by SUB to END	7-58
35	EXIT TASK	Terminates its own task which is in progress	7-59
36	FOR to NEXT	Performs loop processing until the variable-specified value is exceeded	7-60
37	GOSUB to RETURN	Jumps to a sub-routine	7-61
38	GOTO	Executes an unconditional jump to the specified line	7-62

39	HALT	Stops the program and performs a reset	7-63
40	HALTALL	Stops all programs and performs reset.	7-64
41	HAND	Defines the hand	7-65
	41.1 For SCARA Robots		7-65
	41.2 For Cartesian Robots		7-68
42	HOLD	Temporarily stops the program	7-70
43	HOLDALL	Temporality stops all programs.	7-71
44	IF	Evaluates a conditional expression value, and executes the command in accordance with the conditions	7-72
	44.1 Simple IF statement		7-72
	44.2 Block IF statement		7-73
45	INPUT	Assigns a value to a variable specified from the programming box	7-74
46	INT	Truncates decimal fractions	7-75
47	JTOXY	Performs axis unit system conversions (pulse $\rightarrow$ mm)	7-76
48	LEFT\$	Extracts character strings from the left end	7-77
49	LEFTY	Sets the SCARA robot hand system as a left-hand system	7-78
50	LEN	Acquires a character string length	7-79
51	LET	Assigns values to variables	7-80
52	LO	Arm lock output	7-83
53	LOCx	Specifies/acquires point data for a specified axis or shift data for a specified element.	7-84
54	LSHIFT	Left-shifts a bit	7-86
55	MCHREF	Acquires a machine reference	7-87
56	MID\$	Acquires a character string from a specified position	7-88
57	MO	Outputs a specified value to the MO port (internal output)	7-89
58	MOTOR	Controls the motor power status.	7-90
59	MOVE	Performs absolute movement of all robot axes	7-91
60	MOVEI	Performs relative movement of all robot axes	7-106
61	OFFLINE	Sets a specified communication port to the "offline" mode	7-111
62	ON ERROR GOTO	Jumps to a specified label when an error occurs	7-112
63	ON to GOSUB	Executes the subroutine specified by the <expression> value</expression>	7-113
64	ON to GOTO	Jumps to the label specified by the <expression> value</expression>	7-114
65	ONLINE	Sets the specified communication port to the "online" mode	7-115
66	ORD	Acquires a character code	7-116
67	ORGORD	Specifies/acquires the robot's return-to-origin sequence	7-117
68	ORIGIN	Performs a return-to-origin	7-118

69	OUT	Turns ON the specified port output	7-119
70	OUTPOS	Specifies/acquires the OUT enable position parameter of the robot	7-120
71	PDEF	Defines the pallet used to execute pallet movement commands	7-122
72	PMOVE	Executes a pallet movement command for the robot	7-123
73	Pn	Defines points within a program	7-127
74	PPNT	Creates pallet point data	7-129
75	PRINT	Displays the specified expression value at the programming box	7-130
76	PSHFRC	Specifies/acquires a pushing thrust parameter.	7-131
77	PSHJGSP	$Specifies/acquires\ a\ pushing\ detection\ speed\ threshold\ parameter.$	7-132
78	PSHMTD	Specifies/acquires a pushing type parameter.	7-133
79	PSHRSLT	Acquires the status when PUSH statement ends.	7-134
80	PSHSPD	Specifies/acquires the pushing movement speed parameter.	7-135
81	PSHTIME	Specifies/acquires the pushing time parameter.	7-136
82	PUSH	Executes a pushing operation for specified axes.	7-137
83	RADDEG	Performs a unit conversion (radians $\rightarrow$ degrees)	7-142
84	REM	Inserts a comment	7-143
85	RESET	Turns OFF the bits of specified ports, or clears variables	7-144
86	RESTART	Restarts another task during a temporary stop	7-145
87	RESUME	Resumes program execution after error recovery processing	7-146
88	RETURN	Processing which was branched by GOSUB, is returned to the next line after GOSUB	7-147
89	RIGHT\$	Extracts a character string from the right end of another character string	7-148
90	RIGHTY	Sets the SCARA robot hand system to "Right"	7-149
91	RSHIFT	Shifts a bit value to the right	7-150
92	SELECT CASE to END SELECT	Executes the specified command block in accordance with the <expression> value</expression>	7-151
93	SEND	Sends <read file=""> data to the <write file=""></write></read>	7-152
94	SERVO	Controls the servo status	7-154
95	SET	Turns the bit at the specified output port ON	7-155
96	SHARED	Enables sub-procedure referencing without passing on the variable	7-156
97	SHIFT	Sets the shift coordinates	7-157
98	SIN	Acquires the sine value for a specified value	7-158
99	Sn	Defines the shift coordinates in the program	7-159
100	SO	Outputs a specified value to the serial port	7-160
101	SPEED	Changes the program movement speed	7-161
102	SQR	Acquires the square root of a specified value	7-162

RCX340 Programming Manual

103 START	Starts a new task	7-163
104 STR\$	Converts a numeric value to a character string	7-164
105 SUB to END SUB	Defines a sub-procedure	7-165
106 SUSPEND	Temporarily stops another task which is being executed	7-167
107 SWI	Switches the program being executed	7-168
108 TAN	Acquires the tangent value for a specified value	7-169
109 TCOUNTER	Timer & counter	7-170
110 TIME\$	Acquires the current time	7-171
111 TIMER	Acquires the current time	7-172
<b>112</b> TO	Outputs a specified value to the TO port	7-173
113 TOLE	Specifies/acquires the tolerance parameter	7-174
114 TORQUE	Specifies/acquires the maximum torque command value which can be set for a specified axis	7-175
115 VAL	Converts character strings to numeric values	7-177
116 WAIT	Waits until the conditions of the DI/DO conditional expression are met	7-178
117 WAIT ARM	Waits until the robot axis operation is completed	7-179
118 WEIGHT	Specifies/acquires the tip weight parameter	7-180
119 WEND	Ends the WHILE statement's command block	7-181
120 WHERE	Acquires the arm's current position (pulse coordinates)	7-182
121 WHILE to WEND	Repeats an operation for as long as a condition is met	7-183
122 WHRXY	Acquires the arm's current position in Cartesian coordinates	7-184
<b>123</b> XYTOJ	Converts the Cartesian coordinate data ("mm") to joint coordinate data ("pulse")	7-185
Chapter 8 Data file descri	ription	
1 Overview		8-1
1.1 Data file types		8-1
1.2 Cautions		8-1
2 Program file		8-2
2.1 All programs		8-2
2.2 One program		8-3
3 Point file		8-4
<ul><li>3.1 All points</li><li>3.2 One point</li></ul>		8-4 8-6
υτο μοιπι		0-0
4 Point comment file		8-8
4.1 All point comments		8-8

4.2 One point comment	8-9
5 Parameter file	8-10
5.1 All parameters	8-10
5.2 One parameter	8-12
6 Shift coordinate definition file	8-13
6.1 All shift data	8-13
6.2 One shift definition	8-14
7 Hand definition file	8-15
7.1 All hand data	8-15
7.2 One hand definition	8-16
8 Pallet definition file	8-17
8.1 All pallet definitions	8-17
8.2 One pallet definition	8-19
9 All file	8-21
9.1 All files	8-21
10 Program directory file	8-22
10.1 Entire program directory	8-22
10.2 One program	8-23
11 Parameter directory file	8-24
11.1 Entire parameter directory	8-24
12 Variable file	8-25
12.1 All variables	8-25
12.2 One variable	8-27
13 Constant file	8-28
13.1 One character string	8-28
14 Array variable file	8-29
14.1 All array variables	8-29
14.2 One array variable	8-30
15 DI file	8-31
15.1 All DI information	8-31
15.2 One DI port	8-32
16 DO file	8-33
16.1 All DO information	8-33

CONTENTS RCX340
Programming Manual

16.2 One DO port	8-34
17 MO file	8-35
17.1 All MO information	8-35
17.2 One MO port	8-36
18 LO file	8-37
18.1 All LO information	8-37
18.2 One LO port	8-38
19 TO file	8-39
19.1 All TO information	8-39
19.2 One TO port	8-40
20 SI file	8-41
20.1 All SI information	8-41
20.2 One SI port	8-42
21 SO file	8-43
21.1 All SO information	8-43
21.2 One SO port	8-44
22 EOF file	8-45
22.1 EOF data	8-45
23 Serial port communication file	8-46
23.1 Serial port communication file	8-46
24 SIW file	8-47
24.1 All SIW	8-47
24.2 One SIW data	8-48
25 SOW file	8-49
25.1 All SOW	8-49
25.2 One SOW data	8-50
26 Ethernet port communication file	8-51
26.1 Ethernet port communication file	8-51
Chapter 9 User program examples	
1 Basic operation	9-1
1.1 Directly writing point data in program	9-1
1.2 Using point numbers	9-2

RCX34 Programming Manua

1.3	Using shift coordinates	9-3
1.4	Palletizing	9-4
1.4	.1 Calculating point coordinates	9-4
1.4	2 Utilizing pallet movement	9-6
1.5	DI/DO (digital input and output) operation	9-7
2 A <sub> </sub>	oplication	9-8
2.1	Pick and place between 2 points	9-8
2.2	Palletizing	9-10
2.3	Pick and place of stacked parts	9-12
2.4	Parts inspection (Multi-tasking example)	9-14
2.5	Connection to an external device through RS-232C (example 1)	9-17
2.6	Connection to an external device through RS-232C (example 2)	9-18
Cha	pter 10 Online commands	
1 0	nline Command List	10-1
1.1	Online command list: Function specific	10-1
1.2	Online command list: In alphabetic order	10-4
2 0	peration and setting commands	10-6
2.1	Program operations	10-6
2.2	MANUAL mode operation	10-12
2.3	Clearing output message buffer	10-13
2.4	Setting input data	10-13
3 R	eference commands	10-14
3.1	Acquiring return-to-origin status	10-14
3.2	Acquiring the servo status	10-15
3.3	Acquire motor power status	10-15
3.4	Acquiring the access level	10-16
3.5	Acquiring the break point status	10-16
3.6	Acquiring the mode status	10-17
3.7	Acquiring the sequence program execution status	10-17
3.8	Acquiring the version information	10-18
3.9	Acquiring the current positions	10-18
3.10	Acquiring the tasks in RUN or SUSPEND status	10-19
3.11	Acquiring the tasks operation status	10-20
3.12	Acquiring the shift status	10-20
3.13	Acquiring the hand status	10-21
3.14	Acquiring the remaining memory capacity	10-21
3.15	Acquiring the emergency stop status	10-22
3 16	Acquiring various values	10-22

RCX340 Programming Manual

# **CONTENTS**

4 O	peration commands	10-24
4.1	Absolute reset	10-24
4.2	Return-to-origin operation	10-25
4.3	Manual movement: inching	10-26
4.4	Manual movement: jog	10-27
5 D	ata file operation commands	10-28
5.1	Copy operations	10-28
5.2	Erase	10-29
5.3	Rename program name	10-34
5.4	Changing the program attribute	10-34
5.5	Initialization process	10-35
5.6	Data readout processing	10-37
5.7	Data write processing	10-38
6 U	tility commands	10-39
6.1	Setting the sequence program execution flag	10-39
6.2	Setting the date	10-39
6.3	Setting the time	10-40
7 E	xecuting the robot language independently	10-41
8 C	ontrol codes	10-42
Cha	pter 11 Appendix	
1 R	eserved word list	11-1
2 R	obot Language Lists: Command list in alphabetic order	11-3
3 R	obot Language Lists: Function Specific	11-7
	osot Languago Lioto, i anotion opcomo	11-7
4 F	unctions: in alphabetic order	11-12
5 F	unctions: operation-specific	11-14

Index

# Chapter 1 Writing Programs

1	The YAMAHA Robot Language	1-1
2	Characters	1-1
3	Program Basics	1-1
4	Program Names	1-2
5	Identifiers	1-4
6	LABEL Statement	1-4
7	Comment	1-5
8	Command Statement Format	1-5

# The YAMAHA Robot Language

The YAMAHA robot language was developed by Yamaha Motor Co., Ltd. IM Company for simple and efficient programming to control YAMAHA industrial robots. The YAMAHA robot language is similar to BASIC (Beginner's All-purpose Symbolic Instruction Code) and makes even complex robot movements easy to program. This manual explains how to write robot control programs with the YAMAHA robot language, including actual examples on how its commands are used.

# Characters

The characters and symbols used in the YAMAHA robot language are shown below. Only 1-byte characters can be used.

Alphabetic characters

A to Z, a to z

Numbers

0 to 9

Symbols

• katakana (Japanese phonetic characters)



- Katakana (Japanese phonetic characters) cannot be entered from a programming box. Katakana can be used when communicating with a host computer (if it handles katakana).
- Spaces are also counted as characters (1 space = 1 character).

# **Program Basics**



#### NOTE

 For details regarding subprocedure, refer to "11 CALL" and "105 SUB to END SUB" in Chapter 7.



For details regarding user defined functions, refer to "21 DEF FN" in Chapter 7.

Programs are written in a "1 line = 1 command" format, and every line must contain a command. Blank lines (lines with no command) will cause an error when the program is executed. The program's final line, in particular, must not be blank.

To increase the program's efficiency, processes which are repeated within the program should be written as subroutines or sub-procedures which can be called from the main routine. Moreover, same processing items which occurs in multiple programs should be written as common routines within a program named [COMMON], allowing those processing items to be called from multiple programs.

User functions can be defined for specific calculations. Defined user functions are easily called, allowing even complex calculations to be easily performed.

Multi-task programs can also be used to execute multiple command statements simultaneously in a parallel processing manner.

Using the above functions allows easy creation of programs which perform complex processing.

# **Program Names**

Each program to be created in the robot controller must have its own name.

Programs can be named as desired provided that the following conditions are satisfied:

- Program names may contain no more than 32 characters, comprising a combination of alphanumeric characters and underscores (\_).
- Each program must have a unique name (no duplications).

The 2 program names shown below are reserved for system operations, and programs with these names have a special meaning.

- **SEQUENCE**
- COMMON

The functions of these programs are explained below.

#### A) SEQUENCE

Functions Unlike standard robot programs, the RCX340 Controller allows the execution of highspeed processing programs (sequence programs) in response to robot inputs and outputs (DI, DO, MO, LO, TO, SI, SO). Specify a program name of "SEQUENCE" to use this function, thus creating a pseudo PLC within the controller.

> When the controller is in the AUTO or MANUAL mode, a SEQUENCE program can be executed in fixed cycles (regardless of the program execution status) in response to dedicated DI10 (sequence control input) input signals, with the cycle being determined by the program capacity. For details, see "Sequence program specifications".

> This allows sensors, push-button switches, and solenoid valves, etc., to be monitored and operated by input/output signals.

> Moreover, because the sequence programs are written in robot language, they can easily be created without having to use a new and unfamiliar language.

#### SAMPLE

```
DO(20) = \sim DI(20)
DO(25) = DI(21) AND DI(22)
MO(26) = DO(26) OR DO(25)
```

**REFERENCE** For details, see "Sequence function".

Functions A separate "COMMON" program can be created to perform the same processing in multiple robot programs. The common processing routine which has been written in the COMMON program can be called and executed as required from multiple programs. This enables efficient use of the programming space.

> The sample COMMON program shown below contains two processing items (obtaining the distance between 2 points (SUB \*DISTANCE), and obtaining the area (\*AREA)) which are written as common routines, and these are called from separate programs (SAMPLE 1 and SAMPLE 2).

> When SAMPLE1 or SAMPLE2 is executed, the SUB \*DISTANCE (A!,B!,C!) and the \*AREA routine are executed.

```
SAMPLE
Program name: SAMPLE1
   X! = 2.5
   Y! = 1.2
   CALL *DISTANCE(X!,Y!,REF C!)
   GOSUB *AREA
   PRINT C!, Z!
   HALT
Program name: SAMPLE2
   X! = 5.5
   Y! = 0.2
   CALL *DISTANCE(X!, Y!, REF C!)
   GOSUB *AREA
   PRINT C!, Z!
   HALT
Program name: COMMON ..... Common routine
   SUB *DISTANCE(A!,B!,C!)
      C! = SQR(A!^2 + B!^2)
   END SUB
   *AREA:
      Z!=X!*Y!
   RETURN
```

**REFERENCE** For details, refer to the command explanations given in this manual.

Program Names 1-3

## Identifiers

"Identifiers" are a combination of characters and numerals used for label names, variable names, and procedure names. Identifiers can be named as desired provided that the following conditions are satisfied:

- Identifiers must consist only of alphanumeric characters and underscores (\_). Special symbols cannot be used, and the identifier must not begin with an underscore (\_).
- The identifier length must not exceed 32 characters (all characters beyond the 32th character are ignored).
- The maximum number of usable identifiers varies depending on the length of the identifiers. When all identifier length is 32 characters, the number is at the maximum. Local variables can be used up to 128 (in one program task) and global variables can be used up to 512.
- Variable names must not be the same as a reserved word, or the same as a name defined as a system variable. Moreover, variable name character strings must begin with an alphabetic character. For label names, however, the "\*" mark may be immediately followed by a numeric character.

#### SAMPLE

```
LOOP, SUBROUTINE, GET_DATA
```

REFERENCE For details regarding reserved words, see Chapter 11 "1. Reserved word list".

# 6 LABEL Statement

Defines a <label> on a program line.

#### **Format**

```
*<label> :
```

A <label> must always begin with an asterisk mark (\*), and it must be located at the beginning of the line.

Although a colon mark (:) is required at the end of the <label> when defining it, this mark is not required when specifying the <label> as a jump destination in a program.

- 1. A <label> must begin with an alphabetic or numeric character.
- 2. Alphanumeric and underbars (\_) can be used as the remaining <label> characters. Special symbols, etc., cannot be used.
- 3. The <label> must not exceed 32 characters (all characters beyond the 32th character are ignored).

```
*ST: *ST label is defined.

MOVE P,P0
DO(20) = 1
MOVE P,P1
DO(20) = 0
GOTO *ST Jumps to *ST.

HALT
```

#### Comment

Characters which follow REM or an apostrophe mark (" ' ") are processed as a comment. Comment statements are not executed. Moreover, comments may begin at any point in the line.

```
REM *** MAIN PROGRAM ***

(Main program)

' *** SUBROUTINE ***

(Subroutine)

HALT 'HALT COMMAND...... This comment may begin at any point in the line.
```

# **Command Statement Format**

#### **Format**

```
[<label>:] <statement> [<operand>]
```

One robot language command must be written on a single line and arranged in the format shown below:

- Items enclosed in [] can be omitted. This, however, excludes [] that specifies a robot number, point variable, or shift variable. For these, [] needs to be written directly.
- Items enclosed in < > must be written in a specific format.
- Items not enclosed in < > should be written directly as shown.
- Items surrounded by | | are selectable.
- The label can be omitted. When using a label, it must always be preceded by an asterisk (\*), and it must end with a colon (:) (the colon is unnecessary when a label is used as a branching destination).

For details regarding labels, refer to "6 LABEL Statement" in this chapter.

- Operands may be unnecessary for some commands.
- Programs are executed in order from top to bottom unless a branching instruction is given.

1 line may contain no more than 255 characters.

# Chapter 2 Constants

1	Outline	2-1
2	Numeric constants	2-1
3	Character constants	2-2

# **Outline**

Constants can be divided into two main categories: "numeric types" and "character types". These categories are further divided as shown below.

Category	Туре	Details/Range
Numeric type	Integer type	Decimal constants -1,073,741,824 to 1,073,741,823
	•	Binary constants &B0 to &B11111111
	<del></del>	Hexadecimal constants &H80000000 to &H7FFFFFFF
_	Real type	Single-precision real numbers -999,999.9 to +999,999.9
	<del></del>	Exponential format single-precision real numbers -1.0*10 <sup>38</sup> to +1.0*10 <sup>38</sup>
Character type	Character string	Alphabetic, numeric, special character, or katakana (Japanese) character string of 255 bytes or less.

# Numeric constants

# 2.1 Integer constants

#### 1. Decimal constants

Integers from -1,073,741,824 to 1,073,741,823 may be used.

#### 2. Binary constants

Unsigned binary numbers of 8 bits or less may be used. The prefix "&B" is attached to the number to define it as a binary number.

Range: &B0 (decimal: 0) to &B11111111 (decimal: 255)

#### 3. Hexadecimal constants

Signed hexadecimal numbers of 32 bits or less may be used. The prefix "&H" is attached to the number to define it as a hexadecimal number.

Range: &H80000000 (decimal: -2,147,483,648) to &H7FFFFFFF (decimal: 2,147,483,647)

#### 2.2 Real constants

#### 1. Single-precision real numbers

Real numbers from -999999.9 to +999999.9 may be used.

• 7 digits including integers and decimals. (For example, ".0000001" may be used.)

#### 2. Single-precision real numbers in exponent form

Numbers from  $-1.0*10^{38}$  to  $+1.0*10^{38}$  may be used.

• Mantissas should be 7 digits or less, including integers and decimals.

Examples: -1. 23456E-12

3. 14E0

1. E5



• An integer constant range of -1,073,741,824 to 1,073,741,823 is expressed in signed hexadecimal number as &HC0000000 to &H3FFFFFFF.

# Character constants

Character type constants are character string data enclosed in quotation marks ("). The character string must not exceed 255 bytes in length, and it may contain upper-case alphabetic characters, numerals, special characters, or katakana (Japanese) characters.

To include a double quotation mark (") in a string, enter two double quotation marks in succession.

#### SAMPLE

- "YAMAHA ROBOT"
- "EXAMPLE OF" "A" " " EXAMPLE OF "A"
- PRINT "COMPLETED"
- "YAMAHA ROBOT"

# Chapter 3 Variables


1	Outline	3-1
2	User Variables & System Variables	3-2
3	Variable Names	3-3
4	Variable Types	3-4
5	Array variables	3-5
6	Value Assignments	3-5
7	Type Conversions	3-6
8	Value Pass-Along & Reference Pass-Alo	ong3-6
9	System Variables	3-7
10	Bit Settings	3-17
11	Valid range of variables	3-18
12	Clearing variables	3-19

There are "user variables" which can be freely defined, and "system variables" which have predefined names and functions.

User variables consist of "dynamic variables" and "static variables". "Dynamic variables" are cleared at program editing, program resets, and program switching. "Static variables" are not cleared unless the memory is cleared. The names of dynamic variables can be freely defined, and array variables can also be used.

Variables can be used simply by specifying the variable name and type in the program. A declaration is not necessarily required. However, array variables must be pre-defined by a DIM statement.

#### User variables & system variables



33301-R9-00

REFERENCE

For details regarding array variables, see "5 Array variables" in this chapter.

# **User Variables & System Variables**

#### **User Variables** 2.1

Numeric type variables consist of an "integer type" and a "real type", and these two types have different usable numeric value ranges. Moreover, each of these types has different usable variables (character string variables, array variables, etc.), and different data ranges, as shown below.

Category	Variable Type	Details/Range
Dynamic variables	Numeric type	Integer type variables -1,073,741,824 to 1,073,741,823 (Signed hexadecimal constants: &HC0000000 to &H3FFFFFFF)
	<del></del>	Real variables (single-precision) -1.0*10 <sup>38</sup> to +1.0*10 <sup>38</sup>
	Character type	Character string variables Alphabetic, numeric, special character, or katakana (Japanese) character string of 255 bytes or less.
Static variables	Numeric type	Integer type variables -1,073,741,824 to 1,073,741,823
		Real variables (single-precision) -1.0*10 <sup>38</sup> to +1.0*10 <sup>38</sup>
Array variables	Numeric type	Integer array variables -1,073,741,824 to 1,073,741,823
		Real number array variables (single-precision) -1.0*10 <sup>38</sup> to +1.0*10 <sup>38</sup>
	Character type	Character string array variables Alphabetic, numeric, special character, or katakana (Japanese) character string of 255 bytes or less.

Array variables are dynamic variables.

#### 2.2 **System Variables**

As shown below, system variables have pre-defined names which cannot be changed.

Category	Туре	Details	Specific Examples
Input/output variables	Input variable	External signal / status inputs	DI, SI, SIW, SID
-	Output variable	External signal / status outputs	DO, SO, SOW, SOD
Point variable		Handles point data	Pnnnn
Shift variable		Specifies the shift coordinate No. as a numeric constant or expression.	Sn

**REFERENCE** For details, see "9 System Variables" in this chapter.

3

4

5

6

# 3.1 Dynamic Variable Names

Dynamic variables can be named as desired, provided that the following conditions are satisfied:

- The name must consist only of alphanumeric characters and underscores (\_). Special symbols cannot be used.
- The name must not exceed 32 characters (all characters beyond the 32th character are ignored).
- The name must begin with an alphabetic character.

```
COUNT OUSE is permitted
COUNT123 OUSE is permitted
2COUNT X USE is not permitted
```

- Variable names must not be the same as a reserved word.
- Variable names must not begin with characters used for system variable names (pre-defined variables). These characters include the following: FN, DIn, DOn, MOn, LOn, TOn, SIn, SOn, Pn, Sn, Hn ("n" denotes a numeric value).

SAMPLE	
COUNT	······O Use is permitted
ABS	······× (Reserved word)
FNAME	$\cdots \cdots \times (FN: pre-defined variable)$
S91	$\cdots \cdots \times (Sn: pre-defined variable)$

REFERENCE

For details regarding reserved words, see Chapter 11 "1 Reserved word list".

# 3.2 Static Variable Names

Static variable names are determined as shown below, and these names cannot be changed.

Variable Type	Variable Name
Integer variable	SGIn (n: 0 to 31)
Real variable	SGRn (n: 0 to 31)

Static variables are cleared only when initializing is executed by a SYSTEM mode or online command.

(REFERENCE)

For details regarding clearing of static variables, see "12 Clearing variables" in this chapter.

# 4 Variable Types

The type of variable is specified by the type declaration character attached at the end of the variable name.

However, because the names of static variables are determined based on their type, no type declaration statement is required.

Type Declaration Character	Variable Type	Specific Examples
\$	Character type variables	STR1\$
%	Integer type variables	CONT0%, ACT%(1)
!	Real type variables	CNT1!, CNT1



- If no type declaration character is attached, the variable is viewed as a real type.
- Variables using the same identifier are recognized to be different from each other by the type of each variable.

• ASP_DEF%Integer	ACD DEEN/ LACD DEE 1:00	iables
ASP_DEF Real va	iable $\longrightarrow A3r_DLi$ % and $A3r_DLi$ are different vari	lables.
• ASP_DEF! Real va	iable \	
ASP_DEF Real va	iable $\rightarrow$ ASP_DEF! and ASP_DEF are the same varia	ables.

## 4.1 Numeric variables



#### NOTE

• When a real number is assigned to an integer type variable, the decimal value is rounded off to the nearest whole number. For details, refer to Chapter 4 "1.5 Data format conversion".



#### **NOTE**

 The "!" used in real variables may be omitted.

## Integer variables

Integer variables and integer array elements can handle an integer from -1,073,741,824 to 1,073,741,823 (in signed hexadecimal, this range is expressed as &HC00000000 to &H3FFFFFFF).

```
Examples: R1% = 10

R2\%(2) = R1\% + 10000
```

#### Real variables

Real variables and real array elements can handle a real number from  $-1.0*10^{38}$  to  $1.0*10^{38}$ .

```
Examples: R1! = 10.31 R2! (2) = R1% + 1.98E3
```

# 4.2 Character variables

Character variables and character array elements can handle a character string of up to 255 characters.

Character strings may include alphabetic characters, numbers, symbols and katakana (Japanese phonetic characters).

```
Examples: R1$ = "YAMAHA"
R2$(2) = R1$ + "MOTOR" "YAMAHA MOTOR"
```

# 5 Array variables

Both numeric and character type arrays can be used at dynamic variables.

Using an array allows multiple same-type continuous data to be handled together.

Each of the array elements is referenced in accordance with the parenthesized subscript which appears after each variable name. Subscripts may include integers or <expressions> in up to 3 dimensions.

In order to use an array, a DIM statement must be declared in advance, and the maximum number of elements which can be used is the declared subscripts  $+ 1 (0 \sim \text{number of declared subscripts})$ .



- All array variables are dynamic variables. (For details regarding dynamic variables, see "11 Valid range of variables" in this Chapter.)
- The length of an array variable that can be declared with the DIM statement depends on the program size.

#### **Format**

#### SAMPLE

# Value Assignments

An assignment statement (LET) can also be used to assign a value to a variable.



• "LET" directly specifies an assignment statement, and it can always be omitted.

#### **Format**

```
[LET] <variable> = <expression>
```

Write the value assignment target variable on the left side, and write the assignment value or the <expression> on the right side. The <expression> may be a constant, a variable, or an arithmetic expression, etc.

REFERENCE For details, refer to Chapter 7 "51 LET (Assignment Statement)"

# Type Conversions

When different-type values are assigned to variables, the data type is converted as described below.

- When a real number is assigned to an integer type:
   The decimal value is rounded off to the nearest whole number.
- When an integer is assigned to a real type:
   The integer is assigned as it is, and is handled as a real number.
- When a numeric value is assigned to a character string type:
   The numeric value is automatically converted to a character string which is then assigned.
- When a character string is assigned to numeric type:

  This assignment is not possible, and an error will occur at the program is execution. Use the "VAL" command to convert the character string to a numeric value, and that value is then assigned.

# Value Pass-Along & Reference Pass-Along

A variable can be passed along when a sub-procedure is called by a CALL statement. This passalong can occur in either of two ways: as a value pass-along, or as a reference pass-along.

#### Value pass-along

With this method, the variable's value is passed along to the sub-procedure. Even if this value is changed within the sub-procedure, **the content of the call source variable is not changed.** 

A value pass-along occurs when the CALL statement's actual argument specifies a constant, an expression, a variable, or an array element (array name followed by (<subscript>)).

## Reference pass-along

With this method, the variable's reference (address in memory) is passed along to the sub-procedure. If this value is changed within the sub-procedure, **the content of the call source variable** is also changed.

A reference pass-along occurs when the CALL statement's actual argument specifies an entire array (an array named followed by parenthetical content), or when the actual argument is preceded by "REF".

#### Value pass-along & reference pass-along

# Value pass-along X%=5 CALL \*TEST( X% ) PRINT X% HALT 'SUB ROUTINE SUB \*TEST( A% ) A%=A%\*10 END SUB

```
Execution result: the X% value remains as "5".
```

```
Reference pass-along

X%=5

CALL *TEST( REF X% )

PRINT X%

HALT

SUB ROUTINE

SUB *TEST( A% )

A%=A%*10

END SUB
```

Execution result: the X% value becomes "50".

33302-R7-00

2

2

1

5

6

The following system variables are pre-defined, and other variable names must not begin with the characters used for these system variable names.

Variable Type	Format	Meaning
Point variable	Pnnn / P " [" <expression>"] "</expression>	Specifies a point number.
Shift variable	Sn / S " [" <expression>"] "</expression>	Specifies the shift number as a constant or as an expression.
Parallel input variable	DI(mb), DIm(b)	Parallel input signal status.
Parallel output variable	DO(mb), DOm(b)	Parallel output signal setting and status.
Internal output variable	MO(mb), MOm(b)	Controller's internal output signal setting and status
Arm lock output variable	LO(mb), LOm(b)	Axis-specific movement prohibit.
Timer output variable	TO(mb), TOm(b)	For sequence program's timer function.
Serial input variable	SI(mb), SIm(b)	Serial input signal status.
Serial output variable	SO(mb), SOm(b)	Serial output signal setting and status.
Serial word input	SIW(m)	Serial input's word information status
Serial double-word input	SID(m)	Serial input's double-word information status.
Serial word output	SOW(m)	Serial output's word information status
Serial double-word output	SOD(m)	Serial output's double-word information status.

## 9.1 Point data variable

This variable specifies a point data number with a numeric constant or expression.

# Pnnnnn or P" ["<expression>"]"

Values

n: Point number ...... 0 to 9

Each bracket in quotation marks ("[" "]") must be written. Brackets are not used to indicate an item that may be omitted.

**Functions** A point data number is expressed with a 'P' followed by a number of 5 digits or less, or an expression surrounded by brackets ("[" <expression> "]").

Point numbers from 0 to 29999 can be specified with point variables.

```
Examples: P0
P110
P[A]
P[START_POINT]
P[A(10)]
```

#### Shift coordinate variable 9.2

This variable specifies a shift coordinate number with a numeric constant or expression.

#### **Format**

Snn or S "["<expression>"]"



n: Shift number ...... 0 to 9

Each bracket in quotation marks ("[" "]") must be written. Brackets are not used to indicate an item that may be omitted.

Functions) A shift number is expressed with an 'S' followed by a 2-digits number or an expression surrounded by brackets ("[" <expression> "]"). As a shift number, 0 to 39 can be specified.

```
Examples: S1
         S[A]
         S[BASE]
         S[A(10)]
```



• The "shift coordinate range" for each shift number can be changed from the programming box.

#### 9.3 Parallel input variable

This variable is used to indicate the status of parallel input signals.

#### Format 1

DIm([b, · · · , b])

#### Format 2

 $DI(mb, \cdot \cdot \cdot, mb)$ 



m: port number ...... 0 to 7, 10 to 17, 20 to 27

b: bit definition ...... 0 to 7

If the bit definition is omitted, bits 0 to 7 are all selected.

```
Examples: A%=DI1()
         → Input status of ports DI(17) to DI(10)
           is assigned to variable A%.
         A 0 to 255 integer can be assigned to A%.
        A%=DI5(7,4,0)
         \rightarrow Input status of DI(57), DI(54) and
           DI(50) is assigned to variable A%.
          (If all above signals are 1(ON), then A%=7.)
        A%=DI(27,15,10)
         \rightarrow Input status of DI(27), DI(15) and
           DI(10) is assigned to variable A%.
         (If all above signals except DI(10) are 1 (ON), then A%=6.)
        WAIT DI(21)=1

ightarrow Waits for DI(21) to change to 1(ON).
```



- When specifying multiple bits, specify them from left to right in descending order (large to small).
- A '0' is entered if there is no actual input board.

## 9.4 Parallel output variable

Specifies the parallel output signal or indicates the output status.

#### Format 1

 $DOm([b, \cdot \cdot \cdot, b])$ 

#### Format 2

 $DO(mb, \cdot \cdot \cdot, mb)$ 

Values

Examples: A%=DO2()  $\rightarrow$  Output status of DO(27) to DO(20) is assigned to variable A%. A%=DO5(7,4,0) $\rightarrow$  Output status of DO(57), DO(54) and DO(50) is assigned to variable A%. (If all above signals are 1(ON), then A%=7.) A%=DO(37,25,20) $\rightarrow$  Output status of DO(37), DO(25) and DO(20) is assigned to variable A%. (If all above signals except DO(20) are 1 (ON), then A%=6.) DO3 () =B% → Changes to a status in which the DO(37) to DO(30) output can be indicated by B%. For example, if B% is "123": If a binary number is used, "123" will become "01111011", DO(37) and DO(32) will become "0", and the other bits will become "1". DO4(5,4,0) = &B101



• When specifying multiple bits, specify them from left to right in descending order (large to small).

 $\rightarrow$  DO(45) and DO(40) become "1", and DO(44) becomes "0".

• A '0' is entered if there is no actual input board.

## 9.5

Specifies the controller's internal output signals and indicates the signal status.

#### Format 1

 $MOm([b, \cdot \cdot \cdot, b])$ 

Internal output variable

### Format 2

 $MO(mb, \cdot \cdot \cdot , mb)$ 

## Values

m: port number ...... 0 to 7, 10 to 17, 20 to 27, 30 to 33

b: bit definition ...... 0 to 7

• If the bit definition is omitted, bits 0 to 7 are all selected.

Functions Internal output variables which are used only in the controller, can be changed and referenced. These variables are used for signal communications, etc., with the sequence program. Ports 30 to 33 are for dedicated internal output variables which can only be referenced (they cannot be changed).

Port 30 indicates the status of origin sensors for axes 1 to 8 (in order from bit 0). Port 31 indicates the status of origin sensors for axes 9 to 16 (in order from bit 0).

Each bit sets to '1' when the origin sensor turns ON, and to '0' when OFF.

Port 34 indicates the HOLD status of axes 1 to 8 (in order from bit 0). Port 35 indicates the HOLD status of axes 9 to 16 (in order from bit 0).

Each bit sets to '1' when the axis is in HOLD status, and to '0' when not.

Bit	7	6	5	4	3	2	1	0	
Port 30	Axis 8	Axis 7	Axis 6	Axis 5	Axis 4	Axis 3	Axis 2	Axis 1	
Port 31	Axis 16	Axis 15	Axis 14	Axis 13	Axis 12	Axis 11	Axis 10	Axis 9	
	Origin sensor statuses 0: OFF / 1: ON (Axis 1 is not connected)								
Port 34	Axis 8	Axis 7	Axis 6	Axis 5	Axis 4	Axis 3	Axis 2	Axis 1	
Port 35	1				Axis 12			Axis 9	
	Hold status 0: RELEASE / 1: HOLD (Axis 1 is not connected)								



- Axes where no origin sensor is connected are always ON.
- Being in HOLD status means that the axis movement is stopped and positioned within the target point tolerance while the servo is still turned ON.
- When the servo turns OFF, the HOLD status is released.
- Axes not being used are set to '1'.
- The status of each axis in order from the smallest axis number used by robot 1 is maintained. Example) In the case of a configuration where robot 1 has 5 axes and robot 2 has 4 axes, bits 0 to 4 of port 30 indicate the status of axes 1 to 5 of robot 1, bits 5 to 7 of port 30 indicate the status of axes 1 to 3 of robot 2, and bit 0 of port 31 indicates the status of axis 4 of robot 2.

```
Examples: A%=MO2 ()

→ Internal output status of MO(27) to

MO(20) is assigned to variable A%.

A%=MO5(7,4,0)

→ Internal output status of MO(57), MO(54)

and MO(50) is assigned to variable A%.

(If all above signals are 1 (ON), then A%=7.)

A%=MO(37,25,20)

→ Internal output status of MO(37), MO(25)

and MO(20) is assigned to variable A%.

(If all above signals except MO(25) are 1 (ON), then A%=5.)
```



• When specifying multiple bits, specify them from left to right in descending order (large to small).

## 9.6 Arm lock output variable

Specifies axis-specific movement prohibit settings.

#### Format 1

 $LOm([b, \cdot \cdot \cdot, b])$ 

#### Format 2

 $LO(mb, \cdot \cdot \cdot, mb)$ 

Values

m : port number ...... 0, 1 b : bit definition ..... 0 to 7

• If the bit definition is omitted, bits 0 to 7 are all selected.

Functions The contents of this variable can be output and referred to as needed.

Of Port 0, bits 0 to 7 respectively correspond to axes 1 to 8, and of port 1, bits 0 to respectively correspond to axes 9 to 16.

When this bit is ON, movement on the corresponding axis is prohibited.

```
Examples: A%=LOO()

→ Arm lock status of LO(07) to LO(00) is assigned to variable A%.

A%=LOO(7,4,0)

→ Arm lock status of LO(07), LO(04) and LO(00) is assigned to variable A%.

(If all above signals are 1 (ON), then A%=7.)

A%=LOO(06,04,01)

→ Arm lock status of LO(06), LO(04) and LO(01) is assigned to variable A%.

(If all above signals except LO(01) are 1 (ON), then A%=6.)
```



- When specifying multiple bits, specify them from left to right in descending order (large to small).
- Servo OFF to ON switching is disabled if an arm lock is in effect at even 1 axis.
- When performing JOG movement in the MANUAL mode, axis movement is possible at axes where an arm lock status is not in effect, even if an arm lock status is in effect at another axis.
- When executing movement commands from the program, etc., the "12.3 XX.Arm lock" error will occur if an arm lock status is in effect at the axis in question.
- Arm locks sequentially correspond to axes in order from the axis with the smallest axis number used by robot 1.

Example) In the case of a configuration where robot 1 has 5 axes and robot 2 has 4 axes, the status of axes 1 to 5 of robot 1 is set by bits 0 to 4 of port 0, the status of axes 1 to 3 of robot 2 is set by bits 5 to 7 of port 0, and the prohibition of motion of axis 4 of robot 2 is set by bit 0 of port 1.

## 9.7 Timer output variable

This variable is used in the timer function of a sequence program.

#### Format 1

 $TOm([b, \cdot \cdot \cdot, b])$ 

#### Format 2

 $TO(mb, \cdot \cdot \cdot, mb)$ 

### Values

m : port number ...... 0, 1 b : bit definition ..... 0 to 7

• If the bit definition is omitted, bits 0 to 7 are all selected.

Functions The contents of this variable can be changed and referred to as needed.

Timer function can be used only in the sequence program. If this variable is output in a normal program, it is an internal output.

For details regarding sequence program usage examples, refer to the timer usage examples given in "Input/output variables".

```
Examples: A%=TOO()

→ Status of TO(07) to TO(00) is assigned
    to variable A%.

A%=TOO(7,4,0)

→ Status of TO(07), TO(04) and TO(00) is
    assigned to variable A%.

(If all above signals are 1 (ON), then A%=7.)

A%=TO(06,04,01)

→ Status of TO(06), TO(04) and TO(01) is
    assigned to variable A%.

(If all above signals except TO(01) are 1
    (ON), then A%=6.)
```



• When specifying multiple bits, specify them from left to right in descending order (large to small).

## 9.8 Serial input variable

This variable is used to indicate the status of serial input signals.

#### Format 1

```
SIm([b, \cdot \cdot \cdot, b])
```

#### Format 2

```
SI(mb, \cdot \cdot \cdot, mb)
```

Values

```
m : port number ...... 0 to 7, 10 to 17, 20 to 27 b : bit definition ...... 0 to 7
```

• If the bit definition is omitted, bits 0 to 7 are all selected.

```
Examples: A%=SI1()
    → Input status of ports SI(17) to SI(10)
    is assigned to variable A%.
    A%=SI5(7,4,0)
    → Input status of SI(57), SI(54) and
        SI(50) is assigned to variable A%.
    (If all above signals are 1(ON), then A%=7.)
    A%=SI(27,15,10)
    → Input status of SI(27), SI(15) and
        SI(10) is assigned to variable A%.
    (If all above signals except SI(10) are 1
        (ON), then A%=6.)
    WAIT SI(21)=1
    → Waits until SI(21) sets to 1 (ON).
```



- When specifying multiple bits, specify them from left to right in descending order (large to small).
- A '0' is entered if there is no actual serial board.

## 9.9 Serial output variable

This variable is used to define the serial output signals and indicate the output status.

#### Format 1

 $SOm([b, \cdot \cdot \cdot, b])$ 

#### Format 2

 $SO(mb, \cdot \cdot \cdot, mb)$ 



- m: port number ...... 0 to 7, 10 to 17, 20 to 27
- b: bit definition ...... 0 to 7
- If the bit definition is omitted, bits 0 to 7 are all selected.

```
Examples: A%=SO2()
         \rightarrow Output status of SO(27) to SO(20) is
           assigned to variable A%.
        A%=SO5(7,4,0)
         \rightarrow Output status of SO(57), SO(54) and
           SO(50) is assigned to variable A%.
         (If all above signals are 1(ON), then A%=7.)
        A%=SO(37,25,20)
         \rightarrow Output status of SO(37), SO(25) and
           SO(20) is assigned to variable A%.
         (If all above signals except SO(25) are 1
         (ON), then A%=5.)
        SO3()=B%
         → Changes to a status in which the DO(37)
           to DO(30) output can be indicated by B%.
         For example, if B% is "123": If a binary
         number is used, "123" will become
         "01111011", DO(37) and DO(32) will become
```



• When specifying multiple bits, specify them from left to right in descending order (large to small).

"0", and the other bits will become "1".

 $\rightarrow$  DO(45) and DO(40) become "1", and DO(44) becomes "0".

• External output is unavailable if the serial port does not actually exist.

SO4(5,4,0) = &B101

This variable indicates the status of the serial input word information.

#### **Format**

SIW(m)



m: Port No. 2 to 15

The acquisition range is 0 (&H0000) to 65535 (&HFFFF).

```
Examples: A%=SIW(2)

→ The input state from SIW (2) is assigned to variable A%.

A%=SIW(15)

→ The input state from SIW (15) is assigned to variable A%.
```



- The information is handled as unsigned word data.
- '0' is input if the serial port does not actually exist.

## 9.11 Serial double word input

This variable indicates the state of the serial input word information as a double word.

#### **Format**

SID(m)



m: Port No. 2, 4, 6, 8, 10, 12, 14

The acquisition range is -1073741824 (&HC0000000) to 1073741823 (&H3FFFFFFF).

```
Examples: A%=SID(2)

→ The input state from SIW (2) , SIW (3)

is assigned to variable A%.

A%=SID(14)

→ The input state from SIW (14), SIW (15)

is assigned to variable A%.
```



- The information is handled as signed double word data.
- '0' is input if the serial port does not actually exist.
- An error will occur if the value is not within the acquisition range (&H80000000 to &HBFFFFFFF, &H40000000 to &H7FFFFFFF.)
- The lower port number data is placed at the lower address. For example, if SIW(2) =&H2345,SIW(3) =&H0001, then SID(2) =&H000123245.

System Variables 3-15

2

3

Λ

5

## 9.12 Serial word output

Outputs to the serial output word information or indicates the output status.

#### **Format**

SOW (m)



m: Port No. 2 to 15

The output range is 0 (&H0000) to 65535 (&HFFFF).

Note that if a negative value is output, the low-order word information will be output after being converted to hexadecimal.

#### Examples: A%=SOW(2)

 $\rightarrow$  The output status from SOW (2) is assigned to variable A%.

SOW (15) = A%

→ The contents of variable A% are assigned in SOW (15).

If the variable A% value exceeds the output range, the low-order word information will be assigned. SOW(15) = -255

- $\rightarrow$  The contents of -255 (&HFFFFFF01) are assigned to SOW (15).
- -255 is a negative value, so the low-order word information (&HFF01) will be assigned.



- The information is handled as unsigned word data.
- If a serial board does not actually exist, the information is not output externally.
- If a value exceeding the output range is assigned, the low-order 2-byte information is output.

## 9.13 Serial double word output

Output the status of serial output word information in a double word, or indicates the output status.

## Format

SOD(m)



m: Port No. 2, 4, 6, 8, 10, 12, 14

The output range is -1073741824 (&HC0000000) to 1073741823 (&H3FFFFFF).

Examples: A%=SOD(2)

 $\rightarrow$  The input status from SOW (2) is assigned to variable A%. SOD (14) = A%

 $\rightarrow$ The contents of variable A% are assigned in SOD (14).

- The information is handled as signed double word data.
- If a serial board does not actually exist, the information is not output externally.
- An error will occur if the value is not within the output range (&H80000000 to &HBFFFFFF, &H40000000 to &H7FFFFFF.)
- The lower port number data is placed at the lower address. For example, if SOW(2) =&H2345,SOW(3) =&H0001, then SOD(2) =&H000123245.

## Bit Settings

10

Bits can be specified for input/output variables by any of the following methods.

## 1. Single bit

To specify only 1 of the bits, the target port number and bit number are specified in parentheses. The port number may also be specified outside the parentheses.

```
Programming example: DOm(b)DOm(b)

Example: DO(25) Specifies bit 5 of port 2.

DO2(5)
```

## 2. Same-port multiple bits

To specify multiple bits at the same port, those bit numbers are specified in parentheses (separated by commas) following the port number.

The port number may also be specified in parentheses.

```
Programming example: DOm(b,b,...,b) DO(mb,mb,...,mb)

Example: DO2(7,5,3) Specifies DO(27), DO(25), DO(23)

DO(27,25,23)
```

## 3. Different-port multiple bits

To specify multiple bits at different ports, the port number and the 2-digit bit number must be specified in parentheses and must be separated by commas.

```
Programming example: DO(mb,mb,...,mb)
Example: DO(37,25,20) Specifies DO(37), DO(25), DO(20).
```

## 4. All bits of 1 port

To specify all bits of a single port, use parentheses after the port number. Methods 2 and 3 shown above can also be used.

```
Programming example: DOm()

Example: DO2() Specifies all the DO(27) to DO(20) bits

→The same result can be obtained by the following:

DO(27,26,25,24,23,22,21,20)

or,

DO2(7,6,5,4,3,2,1,0)
```

.

1

5

## 11

Variable branching occurs as shown below.

## 11.1 Valid range of dynamic variables

Valid range of variables

Dynamic variables are divided into global variables and local variables, according to their declaration position in the program. Global and local variables have different valid ranges.

Variable Type	Explanation
Global variables	Variables are declared outside of sub-procedures (outside of program areas enclosed by a SUB statement and END SUB statement). These variables are valid throughout the entire program.
Local variables	Variables are declared within sub-procedures and are valid only in these sub-procedures.

## 11.2 Valid range of static variables

Static variable data is not cleared when a program reset occurs. Moreover, variable data can be changed and referenced from any program.

The variable names are determined as shown below (they cannot be named as desired).

Variable type	Variable name		
Integer variable	SGIn (n: 0 to 31)		
Real variable	SGRn (n: 0 to 31)		

## 11.3 Valid range of dynamic array variables

Dynamic array variables are classified into global array variables and local array variables according to their declaration position in the program.

Variable Type	Explanation
Global variables	Variables are declared outside of sub-procedures (outside of program areas enclosed by a SUB statement and END SUB statement). These variables are valid throughout the entire program.
Local variables	Variables are declared within sub-procedures and are valid only in these sub-procedures.



- For details regarding arrays, refer to Chapter 3 "5 Array variables".
- A variable declared at the program level can be referenced from a sub-procedure without being passed along as a dummy argument, by using the SHARED statement (for details, refer to Chapter 7 "96 SHARED").

## 12 Clearing variables

## 12.1 Clearing dynamic variables

In the cases below, numeric variables are cleared to zero, and character variables are cleared to a null string. The variable array is cleared in the same manner.

- When a program is edited.
- When program switching occurs (including SWI command execution).
- When program compiling occurs.
- When a program reset occurs.
- When dedicated input signal DI15 (program reset input) was turned on while the program was stopped in AUTO mode.
- When either of the following is initialized by an initialization operation.
  - 1. Program memory
  - 2. Entire memory
- When any of the following online commands was executed.
   @RESET, @INIT PGM, @INIT MEM, @INIT ALL, @SWI
- When the HALT statement was executed in the program.

## 12.2 Clearing static variables

In the cases below, integer variables and real variables are cleared to zero.

- When the following is initialized by an initialization operation.
   Entire memory
- When any of the following online commands was executed.@INIT MEM, @INIT ALL



• Static variable values are not cleared even if the program is edited.

2

3

4

5

# Chapter 4 Expressions and Operations

1	Arithmetic operations	4-1
2	Character string operations	4-4
3	Point data format	4-5
4	DI/DO conditional expressions	4-6

## **Arithmetic operations**

## 1.1 Arithmetic operators

Operators	Usage Example	Meaning
+	A+B	Adds A to B
-	A-B	Subtracts B from A
*	A*B	Multiplies A by B
/	A/B	Divides A by B
٨	A^B	Obtains the B exponent of A (exponent operation)
-	-A	Reverses the sign of A
MOD	A MOD B	Obtains the remainder A divided by B

When a "remainder" (MOD) operation involves real numbers, the decimal value is rounded off to the nearest whole number which is then converted to an integer before the calculation is executed. The result represents the remainder of an integer division operation.

Examples: A=15 MOD 2 
$$\rightarrow$$
 A=1(15/2=7...1)  
A=17.34 MOD 5.98  $\rightarrow$  A=2(17/5=3...2)

## 1.2 Relational operators

Relational operators are used to compare 2 values. If the result is "true", a "-1" is obtained. If it is "false", a "0" is obtained.

Operators	Usage Example	Meaning
=	A=B	"-1" if A and B are equal, "0" if not.
<>, ><	A<>B	"-1" if A and B are unequal, "0" if not.
<	A <b< td=""><td>"-1" if A is smaller than B, "0" if not.</td></b<>	"-1" if A is smaller than B, "0" if not.
>	A>B	"-1" if A is larger than B, "0" if not.
<=, =<	A<=B	"-1" if A is equal to or smaller than B, "0" if not.
>=, =>	A>=B	"-1" if A is equal to or larger than B, "0" if not.

Examples: 
$$A=10>5$$
  $\rightarrow$  Since 10 > 5 is "true",  $A=-1$ .



• When using equivalence relational operators with real variables and real arrays, the desired result may not be obtained due to the round-off error.

Examples: ......A=2 B=SQR(A!) IF A!=B!\*B! THEN...  $\rightarrow$  In this case, A! will be unequal to B!\*B!.

## 1.3 Logic operations

Logic operators are used to manipulate 1 or 2 values bit by bit. For example, the status of an I/O port can be manipulated.

- Depending on the logic operation performed, the results generated are either 0 or 1.
- Logic operations with real numbers convert the values into integers before they are executed.

Operators	Functions	Meaning
NOT, ~	Logical NOT	Reverses the bits.
AND, &	Logical AND	Becomes "1" when both bits are "1".
OR,	Logical OR	Becomes "1" when either of the bits is "1".
XOR	Exclusive OR	Becomes "1" when both bits are different.
EQV	Logical equivalence operator	Becomes "1" when both bits are equal.
IMP	Logical implication operator	Becomes "0" when the first bit is "1" and the second bit is "0".

Examples: A%=NOT 13.05  $\rightarrow$  "-14" is assigned to A% (reversed after being rounded off to 13).

Bit	7	6	5	4	3	2	1	0
13	0	0	0	0	1	1	0	1
NOT 13=-14	1	1	1	1	0	0	1	0

Examples: A%=3 AND 10  $\rightarrow$  "2" is assigned to A%

Bit	7	6	5	4	3	2	1	0
3	0	0	0	0	0	0	1	1
10	0	0	0	0	1	0	1	0
3 AND 10 = 2	0	0	0	0	0	0	1	0

Examples: A%=3 OR 10  $\rightarrow$  "11" is assigned to A%

Bit	7	6	5	4	3	2	1	0
3	0	0	0	0	0	0	1	1
10	0	0	0	0	1	0	1	0
3 OR 10 = 11	0	0	0	0	1	0	1	1

Examples: A%=3 XOR 10  $\rightarrow$  "9" is assigned to A%

Bit	7	6	5	4	3	2	1	0
3	0	0	0	0	0	0	1	1
10	0	0	0	0	1	0	1	0
3 XOR 10 = 9	0	0	0	0	1	0	0	1

## 1.4

## Priority of arithmetic operation

Operations are performed in the following order of priority. When two operations of equal priority appear in the same statement, the operations are executed in order from left to right.

Priority Rank	Arithmetic Operation
1	Expressions included in parentheses
2	Functions, variables
3	^ (exponents)
4	Independent "+" and "-" signs (monominal operators)
5	* (multiplication), / (division)
6	MOD
7	+ (addition), - (subtraction)
8	Relational operators
9	NOT, ~ (Logical NOT)
10	AND, & (logical AND)
11	OR,  , XOR (Logical OR, exclusive OR)

## 1.5 Data format conversion

Data format is converted in cases where two values of different formats are involved in the same operation.

1. When a real number is assigned to an integer, decimal places are rounded off.

Examples: A%=125.67

→ A%=126

When integers and real numbers are involved in the same operation, the result becomes a real number.

Examples:  $A(0) = 125 * 0.25 \rightarrow A(0) = 31.25$ 

When an integer is divided by an integer, the result is an integer with the remainder discarded.

Examples: A(0) = 100/3

 $\rightarrow$  A(0)=33

#### Character string operations 2

#### 2.1 Character string connection

Character strings may be combined by using the "+" sign.

```
SAMPLE
A$="YAMAHA"
B$="ROBOT"
C$="LANGUAGE"
D$="MOUNTER"
E$=A$+" "+B$+" "+C$
F$=A$+" "+D$
PRINT E$
PRINT F$
Results: YAMAHA ROBOT LANGUAGE
         YAMAHA MOUNTER
```

#### 2.2 Character string comparison

Characters can be compared with the same relational operators as used for numeric values. Character string comparison can be used to find out the contents of character strings, or to sort character strings into alphabetical order.

- In the case of character strings, the comparison is performed from the beginning of each string, character by character.
- If all characters match in both strings, they are considered to be equal.
- Even if only one character in the string differs from its corresponding character in the other string, then the string with the larger (higher) character code is treated as the larger string.
- When the character string lengths differ, the longer of the character strings is judged to be the greater value string.

All examples below are "true".

```
Examples:
           "AA"<"AB"
           "X&">"X#"
           "DESK"<"DESKS"
```

## 5

#### **NOTE**

 The data format is common for axes 1 to 6 for both the joint coordinate format and the Cartesian coordinate format.

Point data format

- Plus (+) signs can be omitted.
- The first arm and the second arm rotation information is not available on any robot model except the YK500TW.

There are two types of point data formats: joint coordinate format and Cartesian coordinate format. Point numbers are in the range of 0 to 29999.

Coordinate Format	Data Format	Explanation
Joint coordinate format	± nnnnnnn	This is a decimal integer constant of 7 digits or less with a plus or minus sign, and can be specified from –6144000 to 6144000. Unit: [pulses]
Cartesian coordinate format	± nnn.nn to ± nnnnnnn	This is a decimal fraction of a total of 7 digits including 3 or less decimal places. Unit: [mm] or [degrees]

When setting an extended hand system flag for SCARA robots, set either 1 or 2 at the end of the data. If a value other than 1 or 2 is set, or if no value is designated, 0 will be set to indicate that no hand system flag is set.

Hand System	Data Value
RIGHTY (right-handed system)	1
LEFTY (left-handed system)	2

On the YK500TW model robot, the first arm and the second arm movement range is extended beyond 360 degrees (The working envelope for both the first arm and second arm is -225° to +225°). Therefore, attempts to convert Cartesian coordinate data ("mm" units) to joint coordinate data (pulse units) will result in multiple solutions, making the position impossible to determine.

In order to obtain the correct robot position and arm posture when converting to joint coordinates, the first arm and the second arm rotation information is added after the "mm" units point data's extended hand system flag.

The Cartesian coordinate data ("mm" units) is then converted to joint coordinate data (pulse units) according to the specified the first arm and the second arm rotation information.

To set extended the first arm and the second arm rotation information at the YK500TW model robot, a "-1", "0", or "1" value must be specified after the hand system flag. Any other value, or no value, will be processed as "0".

Arm rotation information	Data Value
"mm" $\rightarrow$ pulse converted angle data x (*1) range: -180° < x <= 180°	0
"mm" $\rightarrow$ pulse converted angle data x (*1) range: 180° < x <= 540°	1
"mm" $\rightarrow$ pulse converted angle data x (*1) range: -540° < x <= -180°	-1

<sup>\*1:</sup> The joint-coordinates-converted pulse data represents each arm's distance (converted to angular data) from its mechanical origin point.

## 4 DI/DO conditional expressions

DI/DO conditional expressions may be used to set conditions for WAIT statements and STOPON options in MOVE statements.

Numeric constants, variables and arithmetic operators that may be used with DI/DO conditional expressions are shown below.

Constant

Decimal integer constant, binary integer constant, hexadecimal integer constant

Variables

Global integer type, global real number type, input/output type

• Operators

Relational operators, logic operators

- Operation priority
  - 1. Relational operators
  - 2. NOT, ~
  - 3. AND, &
  - 4. OR, |, XOR

Examples: WAIT DI(31) = 1 OR DI(34) = 1

 $\rightarrow$  The program waits until either DI31 or DI34 turns ON.

3

4

# Chapter 5 Multiple Robot Control

1	Overview5-1
2	Command list with a robot specified 5-2

2

RCX340 can be used to control multiple robots (up to 4).

The multitask function also enables multiple robots to move asynchronously.

To use this function, settings for multiple robots or settings for auxiliary axes must be made in the system prior to shipment.

The following settings are possible to the axes of robots.


- Robot 1 (4 axes)
- Robot 1 (1 axis) + robot 2 (1 axis) + robot 3 (1 axis) + robot 4 (1 axis)
- Robot 1 (6 axes) + robot 2 (2 axes) (when using the YC-LINK/E option)
- Robot 1 (4 axes) + robot 2 (4 axes) (when using the YC-LINK/E option)
- Robot 1 (2 axes) + robot 2 (2 axes)
- Robot 1 (4 axes) + robot 2 (4 axes) + robot 3 (4 axes) + robot 4 (4 axes) (when using the YC-LINK/E option)

Each robot consists of normal axes and auxiliary axes.


When using one robot without auxiliary axes, the setting is made only to normal axes.

### **Axes configuration**


#### 1. For robot 1




#### 2. For robot 1 and robot 2



#### 3. For 1 robot with no additional axes used



### 4. When no auxiliary axes are set to two robots



3501-R9-00

Л

5

## Command list with a robot specified

The special commands and functions for robot movements and coordinate control are common for all robots. A robot can be specified with an option of a command. Main commands are shown below.

Operator	Comma	nd name
Robot movement	DRIVE MOVE PMOVE WAIT ARM	DRIVEI MOVEI SERVO
Coordinate control	CHANGE LEFTY SHIFT	HAND RIGHTY
Status change	ACCEL ASPEED DECEL OUTPOS TOLE	ARCHP1 AXWEIGHT ORGORD SPEED WEIGHT
Point operation	JTOXY XYTOJ	WHERE WHRXY
Parameter reference	ACCEL AXWEIGHT ORGORD TOLE	ARCHP1 DECEL OUTPOS WEIGHT
Status reference	ABSRPOS ARMSEL	ARMCND MCHREF
Torque control	DRIVE (with torque limit TORQUE TRQTIME	setting option) TRQSTS CURTRQ

• An axis specified as an auxiliary axis cannot be moved with the MOVE, MOVEI and PMOVE commands. Use the DRIVE or DRIVEI command to move it.

# Chapter 6 Multi-tasking

1	Outline	6-1
2	Task definition	6-1
3	Task status and transition	6-2
4	Multi-task program example	6-8
5	Sharing the data	6-8
6	Cautionary Items	6-9

## **Outline**

The multi-task function performs multiple processing simultaneously in a parallel manner, and can be used to create programs of higher complexity. Before using the multi-tasking function, read this section thoroughly and make sure that you fully understand its contents.

Multi-tasking allows executing two or more tasks in parallel. However, this does not mean that multiple tasks are executed simultaneously because the controller has only one CPU to execute the tasks. In multi-tasking, the CPU time is shared among multiple tasks by assigning a priority to each task so that they can be executed efficiently.

- A maximum of 16 tasks (task 1 to task 16) can be executed in one program.
- Tasks can be prioritized and executed in their priority order (higher priority tasks are executed first).
- The priority level can be set to any level between 17 and 47.
- Smaller values have higher priority, and larger values have lower priority (High priority: 17 ⇔ 47: low priority).

## Task definition

A task is a set of instructions which are executed as a single sequence. As explained below, a task is defined by assigning a label to it.

- 1. Create one program that describes a block of the command which is to be defined as a task.
- 2. In the START statement of the program that will be a main task, specify the program created at step 1 above. Task Nos. are then assigned, and the program starts.

```
SAMPLE
' MAIN TASK (TASK1)
START *IOTASK, T2 ······ *IOTASK is started as Task 2
*ST1:
MOVE P, P1, P0
   IF DI(20) = 1 THEN
     HALT
   ENDIF
GOTO *ST
HALT
Program name: SUB PGM
*SUBPGM:
' SUB TASK (TASK2)
*IOTASK: ..... Task 2 begins from here
   IF DI(21)=1 THEN
     DO(30) = 1
   ELSE
     DO(30) = 0
   ENDIF
GOTO *SUBPGM ····· Task 2 processing ends here
EXIT TASK
```

\_

3

Л

5

## Task status and transition

There are 6 types of task status.

#### 1. STOP status

A task is present but the task processing is stopped.

#### 2. RUN status

A task is present and the task processing is being executed by the CPU.

#### 3. READY status

A task is present and ready to be allocated to the CPU for task processing.

#### 4. WAIT status

A task is present and waiting for an event to begin the task processing.


#### 5. SUSPEND status

A task is present but suspended while waiting to begin the task processing.

#### 6. NON EXISTENT status

No tasks exist in the program. (The START command is used to perform a call).

#### Task state transition



33601-R9-00

## 3.1 Starting tasks

When the program is being executed in the AUTO mode, Task 1 (main task) is automatically selected and placed in a RUN status when the program begins. Therefore, the delete, forced wait, forced end commands, etc., cannot be executed for Task 1.

Other tasks (2 to 8 subtasks) will not be called simply by executing the program. The START command must be used at Task 1 in order to call, start, and place these tasks in a READY status.





• The RESTART, SUSPEND, EXIT TASK, and CUT commands cannot be executed at Task 1.

Task scheduling determines the priority to be used in allocating tasks in the READY(execution enabled) status to the CPU and executing them.

When there are two or more tasks which are put in the READY status, ready queues for CPU allocation are used to determine the priority for executing the tasks. One of these READY status tasks is then selected and executed (RUN status).

Only tasks with the same priority ranking are assigned to a given ready queue. Therefore, where several tasks with differing priority rankings exist, a corresponding number of ready queues are created. Tasks within a given ready queue are handled on a first come first serve (FCFS) basis. The task where a READY status is first established has priority. The smaller the number, the higher the task priority level.





33602-R7-00

A RUN status task will be moved to the end of the ready queue if placed in a READY status by any of the following causes:


- 1) A WAIT status command was executed.
- 2) The CPU occupation time exceeds a specified time.
- 3) A task with a higher priority level is put in READY status.

# -

#### NOTE

When the prescribed CPU occupation time elapses, the active command is ended, and processing moves to the next task. However, if there are no other tasks of the same or higher priority (same or higher ready queue), the same task will be executed again.





33603-R7-00

2

3

4

5

## 3.3 Condition wait in task

A task is put in the WAIT status (waiting for an event) when a command causing a wait status is executed for that task. At this time, the transition to READY status does not take place until the wait condition is canceled.

#### 1. When a command causing a wait status is executed, the following transition happens.

- $\blacksquare$  Task for which a command causing a wait status is executed  $\rightarrow$  WAIT status
- Task at the head of the ready queue with higher priority → RUN status



• For example, when a MOVE statement (a command that establishes a WAIT status) is executed, the CPU sends a "MOVE" instruction to the driver, and then waits for a "MOVE COMPLETED" reply from the driver. This is a "waiting for an event" status. In this case, a WAIT status is established at the task which executed the MOVE command, and that task is moved to the end of the ready queue. A RUN status is then established at the next task.



• If multiple tasks are in WAIT status awaiting the same condition event, or different condition events occur simultaneously, all tasks for which the waited events occur are put in READY status.



## 2. When an event waited by the task in the WAIT status occurs, the following status transition takes place by task scheduling.

- Task in the WAIT status for which the awaited event occurred → READY status However, if the task put in the READY status was at the head of the ready queue with the highest priority, the following transition takes place.
- 1) Task that is currently in RUN status → READY status
- 2) Task at the head of the ready queue with higher priority → RUN status
- In the above MOVE statement example, the task is moved to the end of the ready queue. Then, when a "MOVE COMPLETED" reply is received, this task is placed in READY status.

Tasks are put in WAIT status by the following commands.

Event		Command			
Wait for axis movement to complete	Axis movement command	MOVE PMOVE	MOVEI SERVO	DRIVE WAIT ARM	DRIVEI
	Parameter command	ACCEL DECEL WEIGHT	ARCHP1 OUTPOS	ARCHP2 TOLE	AXWEIGHT ORGORD
	Robot status change command	CHANGE ASPEED	SHIFT SPEED	LEFTY	RIGHTY
Wait for time to elapse		DELAY, SET (Time should be specified.), WAIT ARM (Time should be specified.)			
Wait for condition to be met		WAIT			
Wait for data to send or to be received		SEND			
Wait for print buffer to become empty		PRINT			
Wait for key input		INPUT			



• The tasks are not put in WAIT status if the event has been established before the above commands are executed.

#### Suspending tasks (SUSPEND) 3.4

The SUSPEND command temporarily stops tasks other than task 1 and places them in SUSPEND status. The SUSPEND command cannot be used for task 1.


When the SUSPEND command is executed, the status transition takes place as follows.


Task that executed the SUSPEND command

 $\rightarrow$  RUN status

Specified task

→ SUSPEND status





33604-R7-00

#### Restarting tasks (RESTART) 3.5

Tasks in the SUSPEND status can be restarted with the RESTART command. However, the RESTART command cannot be used for task 1.

When the RESTART command is executed, the status transition takes place as follows.


Task for which the RESTART command was executed

 $\rightarrow$  RUN status

Specified task

→ READY status

## Restarting tasks (RESTART)



33605-R7-00

## 3.6 Deleting tasks


## ■ Task self-delete (EXIT TASK)

Tasks can delete themselves by using the EXIT TASK command and set to the NON EXISTEN (no task registration) status. The EXIT TASK command cannot be used for task 1.

When the EXIT TASK command is executed, the status transition takes place as follows.

- Task that executed the EXIT TASK command
- → NON EXISTEN status
- Task at the head of the ready queue with higher priority
- → RUN status

## Task self-delete (EXIT TASK)



33606-R7-00

## Other-task delete (CUT)

A task can also be deleted and put in the NON EXISTEN (no task registration) status by the other tasks using the CUT command. The CUT command cannot be used for task 1.


When the CUT command is executed, the status transition takes place as follows.

- Task that executed the CUT command
- $\rightarrow RUN$

Specified task

 $\rightarrow$  NON EXISTEN

## Other-task delete (CUT)



33607-R7-00



- If a SUSPEND command is executed for a WAIT-status task, the commands being executed by that task are ended.
- None of these commands can be executed for Task 1.

## **HALT command is executed.** (stop & reset)

The program is reset and all tasks other than task 1 are put in the NON EXISTEN status. Task 1 is put in the STOP status.

#### 2. HOLD command is executed. (temporary stop)

All tasks are put in the STOP status. When the program is restarted, the tasks in the STOP status set to the READY or SUSPEND status.

## STOP key on the programming box is pressed or the interlock signal is cut off. Just as in the case where the HOLD command is executed, all tasks are put in the STOP status. When the program is restarted, the tasks in the STOP status set to the READY status (or, the task is placed in a SUSPEND status after being placed in a READY status).

## 4. When the emergency stop switch on the programming box is pressed or the emergency stop signal is cut off.

All tasks are put in STOP status. At this point, the power to the robot is shut off and the servo sets to the non-hold state.

After the canceling emergency stop, when the program is restarted, the tasks in STOP status are set to the READY or SUSPEND status. However, a servo ON is required in order to restart the robot power supply.



• When the program is restarted without being reset after the tasks have been stopped by a cause other than 1., then each task is processed from the status in which the task stopped. This holds true when the power to the controller is turned off and then turned on.

## Multi-task program example

Tasks are executed in their scheduled order. An example of a multi-task program is shown below.

```
SAMPLE
'TASK1
START *ST2, T2
START *ST3,T3
*ST1:
  DO(20) = 1
  WAIT MO(20) = 1
  MOVE P, P1, P2, Z=0
  IF MO(21)=1 THEN *FIN
GOTO *ST1
*FIN:
CUT T2
HALT
'TASK2
*ST2:
        ····· Task 2 begins here.
   IF DI(20) = 1
     MO(20) = 1
     DELAY 100
  ELSE
     MO(20) = 0
  ENDIF
GOTO *ST2
EXIT TASK ..... Ends here.
'TASK3
        ····· Task 3 begins here.
*ST3:
  IF DI(21) = 0 THEN *ST3
  IF DI(30) = 0 THEN *ST3
  IF DI(33) = 0 THEN *ST3
  MO(21) = 1
EXIT TASK ..... Ends here.
```

## Sharing the data

Point data, shift coordinate definition data, hand definition data, pallet definition data, all global variables and other variables are shared between all tasks.

Execution of each task can be controlled while using the same variables and data shared with the other tasks.



5

• In this case, however, use sufficient caution when rewriting the variable and data because improper changes may cause trouble in the task processing.

2

2

4

5

6

A silence stop may occur if subtasks are continuously started (START command) and ended (EXIT TASK command) by a main task in an alternating manner.

This occurs for the following reason: if the main task and subtask priority levels are the same, a task transition to the main task occurs during subtask END processing, and an illegal task status then occurs when the main task attempts to start a subtask.

Therefore, in order to properly execute the program, the subtask priority level must be set higher than that of the main task. This prevents a task transition condition from occurring during execution of the EXIT TASK command.

In the sample program shown below, the priority level of task 1 (main task) is set as 32, and the priority level of task 2 is set as 31 (the lower the value, the higher the priority).

```
SAMPLE
FLAG1 = 0
*MAIN TASK:
   IF FLAG1=0 THEN
      FLAG1 = 1
      START *TASK2, T2, 31 ······ Task 2 (*TASK2) is started at the
                              priority level of 31.
   ENDIF
GOTO *MAIN TASK
'========
      TASK2
'=======
*TASK2:
   DRIVE (1, P1)
   WAIT ARM(1)
   DRIVE(1,P2)
   WAIT ARM(1)
   FLAG1 = 0
EXIT TASK
HALT
```

# Chapter 7 Robot Language Lists

How to	o read the robot language table .	7-1
Comm	nand list in alphabetic order	7-2
Functi	on Specific	7-6
Functi	ons: in alphabetic order	7-11
Functi	ons: operation-specific	7-13
1	ABS	7-15
2	ABSRPOS	7-16
3	ACCEL	7-17
4	ARCHP1 / ARCHP2	7-18
5	ARMCND	7-20
6	ARMSEL	7-21
7	ARMTYP	7-22
8	ASPEED	7-23
9	ATN / ATN2	7-24
10	AXWGHT	7-25
11	CALL	7-26
12	CHANGE	7-27
13	CHGPRI	7-28
14	CHR\$	7-29
15	COS	7-30


16	<b>CURTQST</b> 7-31
17	<b>CURTRQ</b> 7-32
18	<b>CUT</b> 7-33
19	<b>DATE\$</b> 7-34
20	<b>DECEL</b> 7-35
21	<b>DEF FN</b> 7-36
22	<b>DEGRAD</b> 7-37
23	<b>DELAY</b> 7-38
24	<b>DI</b>
25	<b>DIM</b> 7-40
26	<b>DIST</b>
27	<b>DO</b> 7-42
28	<b>DRIVE</b>
29	<b>DRIVEI</b> 7-49
30	<b>END SELECT</b> 7-54
31	<b>END SUB</b> 7-55
32	<b>ERR / ERL</b> 7-56
33	<b>EXIT FOR</b> 7-57
34	<b>EXIT SUB</b> 7-58
35	<b>EXIT TASK</b>
36	<b>FOR to NEXT</b>
37	<b>GOSUB to RETURN</b> 7-61
38	<b>GOTO</b> 7-62
39	<b>HALT</b> 7-63
40	<b>HALTALL</b>
41	<b>HAND</b> 7-65
42	<b>HOLD</b> 7-70
43	HOLDALL7-71
44	<b>IF</b> 7-72
45	INPUT7-74
46	INT7-75
47	<b>JTOXY</b> 7-76
48	<b>LEFT\$</b>
49	<b>LEFTY</b>
50	<b>LEN</b> 7-79
51	<b>LET</b> 7-80

52	LO7-83
53	LOCx7-84
54	<b>LSHIFT</b> 7-86
55	MCHREF7-87
56	MID\$7-88
57	<b>MO</b> 7-89
58	<b>MOTOR</b> 7-90
59	<b>MOVE</b> 7-91
60	MOVEI7-106
61	<b>OFFLINE</b> 7-111
62	<b>ON ERROR GOTO</b> 7-112
63	<b>ON to GOSUB</b> 7-113
64	ON to GOTO7-114
65	<b>ONLINE</b>
66	<b>ORD</b> 7-116
67	<b>ORGORD</b> 7-117
68	<b>ORIGIN</b> 7-118
69	<b>OUT</b> 7-119
70	<b>OUTPOS</b> 7-120
71	<b>PDEF</b> 7-122
72	<b>PMOVE</b> 7-123
73	<b>Pn</b> 7-127
74	<b>PPNT</b> 7-129
75	<b>PRINT</b> 7-130
76	<b>PSHFRC</b>
77	<b>PSHJGSP</b> 7-132
78	<b>PSHMTD</b> 7-133
79	<b>PSHRSLT</b> 7-134
80	<b>PSHSPD</b> 7-135
81	<b>PSHTIME</b>
82	<b>PUSH</b> 7-137
83	<b>RADDEG</b> 7-142
84	<b>REM</b> 7-143
85	<b>RESET</b> 7-144
86	<b>RESTART</b> 7-145
87	<b>RESUME</b> 7-146

88	<b>RETURN</b> 7-147
89	<b>RIGHT\$</b> 7-148
90	<b>RIGHTY</b> 7-149
91	<b>RSHIFT</b>
92	SELECT CASE to END SELECT7-151
93	<b>SEND</b>
94	<b>SERVO</b> 7-154
95	<b>SET</b> 7-155
96	<b>SHARED</b> 7-156
97	<b>SHIFT</b>
98	<b>SIN</b> 7-158
99	<b>\$n</b> 7-159
100	<b>SO</b> 7-160
101	<b>SPEED</b> 7-161
102	<b>SQR</b> 7-162
103	<b>START</b> 7-163
104	<b>STR\$</b> 7-164
105	<b>SUB to END SUB</b> 7-165
106	<b>SUSPEND</b> 7-167
107	<b>SWI</b> 7-168
108	<b>TAN</b> 7-169
109	<b>TCOUNTER</b> 7-170
110	TIME\$7-171
111	<b>TIMER</b> 7-172
112	TO7-173
113	<b>TOLE</b> 7-174
114	<b>TORQUE</b> 7-175
115	<b>VAL</b> 7-177
116	<b>WAIT</b> 7-178
117	<b>WAIT ARM</b> 7-179
118	<b>WEIGHT</b> 7-180
119	<b>WEND</b> 7-181
120	<b>WHERE</b> 7-182
121	<b>WHILE to WEND</b> 7-183
122	<b>WHRXY</b> 7-184
123	<b>XYTOJ</b> 7-185


## How to read the robot language table

The key to reading the following robot language table is explained below.



(1) No.

Indicates the Item No. where this robot language is explained in detail.



(2) Function

Explains the function of the robot language.

- (3) Online
  - If "O" is indicated at this item, online commands can be used.
  - If " $\triangle$ " is indicated at this item, commands containing operands that cannot partially be executed by online command.
- (4) Type

Indicates the robot language type as "Command" or "Function".

When a command is used as both a "Command" and "Function", this is expressed as follows: Command/Function

# Command list in alphabetic order

No.	Command	Function	Online	Туре
Α				
1	ABS	Acquires the absolute value of a specified value.	-	Command Statements
2	ABSRPOS	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)	-	Command Statements/ Functions
3	ACCEL	Specifies/acquires the acceleration coefficient parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP1	Specifies/acquires the arch position 1 parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP2	Specifies/acquires the arch position 2 parameter of a specified robot.	0	Command Statements/ Functions
5	ARMCND	Acquires the current arm status of a specified robot.	-	Functions
6	ARMSEL	Acquires the current "hand system" setting of a specified robot.	-	Functions
7	ARMTYP	Acquires the "hand system" setting of a specified robot.	-	Functions
8	ASPEED	Specifies/acquires the AUTO movement speed of a specified robot.	0	Command Statements/ Functions
9	ATN	Acquires the arctangent of the specified value.	-	Functions
9	ATN2	Acquires the arctangent of the specified X-Y coordinates.	-	Functions
10	AXWGHT	Specifies/acquires the axis tip weight parameter of a specified robot.	0	Command Statements/ Functions
С				
11	CALL	Calls a sub-procedure.	×	Command Statements
12	CHANGE	Switches the hand of a specified robot.		Command Statements
13	CHGPRI	Changes the priority ranking of a specified task.	0	Command Statements
14	CHR\$	Acquires a character with the specified character code.	-	Functions
15	cos	Acquires the cosine value of a specified value.	-	Functions
16	CURTQST	Acquires the current torque against the rated torque of a specified axis.	-	Functions
17	CURTRQ	Acquires the current torque value of the specified axis of a specified robot.	-	Functions
18	CUT	Terminates a task currently being executed or temporarily stopped.	0	Command Statements
D				
19	DATE\$	Acquires the date as a "yy/mm/dd" format character string.	-	Functions
20	DECEL	Specifies/acquires the deceleration rate parameter of a specified robot.	0	Command Statements/ Functions
21	DEF FN	Defines the functions that can be used by the user.	×	Command Statements
22	DEGRAD	Converts a specified value to radians (↔RADDEG).	-	Functions
23	DELAY	Waits for the specified period (units: ms).	×	Command Statements
24	DI	Acquires the input from the parallel port.	-	Functions
25	DIM	Declares the array variable name and the number of elements.	×	Command Statements
26	DIST	Acquires the distance between 2 specified points.	-	Functions
27	DO	Outputs a specified value to the DO port.	0	Command Statements
28	DRIVE	Moves a specified axis of a specified robot to an absolute position.	0	Command Statements
28	DRIVE	(With T-option) Executes an absolute movement command for a specified axis.	0	Command Statements
	DRIVEI	Moves a specified axis of a specified robot to a relative position.	0	Command Statements

No.	Command	Function	Online	Туре
Е				
30	END SELECT	Terminates the SELECT CASE statement.	×	Command Statements
31	END SUB	Terminates the sub-procedure definition.	×	Command Statements
32	ERL	Gives the line No. where an error occurred.	-	Functions
32	ERR	Gives the error code number of an error which has occurred.	-	Functions
33	EXIT FOR	Terminates the FOR to NEXT statement loop.	X	Command Statements
34	EXIT SUB	Terminates the sub-procedure defined in SUB to END.	X	Command Statements
35	EXIT TASK	Terminates its own task which is in progress.	×	Command Statements
F			•	
36	FOR to NEXT	Controls repetitive operations. Executes the FOR to NEXT statement repeatedly until a specified value is exceeded.	×	Command Statements
G				
37	GOSUB to RETURN	Jumps to a subroutine with the label specified by a GOSUB statement, and executes that subroutine.	×	Command Statements
38	GOTO	Unconditionally jumps to the line specified by a label.	×	Command Statements
Н	<u>'</u>			'
39	HALT	Stops the program and performs a reset.	X	Command Statements
40	HALTALL	Stops and resets all programs.	×	Command Statements
41	HAND	Defines the hand of a specified robot.		Command Statements
42	HOLD	Temporarily stops the program.	×	Command Statements
43	HOLDALL	Temporarily stops all programs.	×	Command Statements
ı	L			
44	l IF	Allows control flow to branch according to conditions.	×	Command Statements
45	INPUT	Assigns a value to a variable specified from the programming box.		Command Statements
46	INT	Acquires an integer for a specified value by truncating all	_	Functions
	IIV I	decimal fractions.		Tunctions
J				
47	JTOXY	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (→XYTOJ)	-	Functions
L				
48	LEFT\$	Extracts a character string comprising a specified number of digits from the left end of a specified character string.	-	Functions
49	LEFTY	Sets the hand system of a specified robot to "Left."	0	Command Statements
50	LEN	Acquires the length (number of bytes) of a specified character string.	-	Functions
51	LET	Executes a specified assignment statement.	0	Command Statements
52	LO	Outputs a specified value to the LO port to enable/disable axis movement.	0	Command Statements
53	LOCx	Specifies/acquires point data for a specified axis or shift data for a specified element.	-	Command Statements/ Functions
54	LSHIFT	Shifts a value to the left by the specified number of bits. (↔RSHIFT)	-	Functions
M				
55	MCHREF	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.	-	Functions
56	MID\$	Extracts a character string of a desired length from a specified character string.	-	Functions
57	МО	Outputs a specified value to the MO port.	0	Command Statements
58	MOTOR	Controls the motor power status.	0	Command Statements
		Performs absolute movement of all axes of a specified robot.		Command Statements

No.	Command	Function	Online	Туре		
60	MOVEI	Performs relative movement of all axes of a specified robot.	0	Command Statements		
0	0					
61	OFFLINE	Sets a specified communication port to the "offline" mode.	0	Command Statements		
62	ON ERROR GOTO	If an error occurs during program execution, this command allows the program to jump to the error processing routine specified by the label without stopping the program, or it stops the program and displays the error message.	×	Command Statements		
63	ON to GOSUB	Jumps to a subroutine with labels specified by a GOSUB statement in accordance with the conditions, and executes that subroutine.	×	Command Statements		
64	ON to GOTO	Jumps to label-specified lines in accordance with the conditions.	×	Command Statements		
65	ONLINE	Sets the specified communication port to the "online" mode.	0	Command Statements		
66	ORD	Acquires the character code of the first character in a specified character string.	-	Functions		
67	ORGORD	Specifies/acquires the axis sequence parameter for performing return-to-origin and an absolute search operation in a specified robot.	0	Command Statements/ Functions		
68	ORIGIN	Performs a return-to-origin.	0	Command Statements		
69	OUT	Turns ON the bits of the specified output ports and the command statement ends.	×	Command Statements		
70	OUTPOS	Specifies/acquires the OUT enable position parameter of a specified robot.	0	Command Statements/ Functions		
Р						
71	PDEF	Defines the pallet used to execute pallet movement commands.	0	Command Statements		
72	PMOVE	Executes the pallet movement command of a specified robot.	0	Command Statements		
73	Pn	Defines points within a program.	0	Command Statements		
74	PPNT	Creates point data specified by a pallet definition number and pallet position number.	-	Functions		
75	PRINT	Displays a character string at the programming box screen.	0	Command Statements		
76	PSHFRC	Specifies/acquires the pushing thrust parameter.	0	Command Statements/ Functions		
77	PSHJGSP	Specifies/acquires the pushing check speed threshold parameter.	0	Command Statements/ Functions		
78	PSHMTD	Specifies/acquires the pushing method parameter.	0	Command Statements/ Functions		
79	PSHRSLT	Acquires the status at the end of the PUSH statement.	-	Functions		
80	PSHSPD	Specifies/acquires the pushing movement speed parameter.	0	Functions		
81	PSHTIME	Specifies/acquires the pushing time parameter.	0	Functions		
82	PUSH	Executes a pushing operation in the axis unit.	0	Command Statements		
R						
83	RADDEG	Converts a specified value to degrees. (↔DEGRAD)	-	Functions		
84	REM	Expresses a comment statement.	×	Command Statements		
85	RESET	Turns the bit of a specified output port OFF.	0	Command Statements		
86	RESTART	Restarts another task during a temporary stop.	0	Command Statements		
87	RESUME	Resumes program execution after error recovery processing.	×	Command Statements		
88	RETURN	Returns the processing branching with GOSUB to the next line of GOSUB.	×	Command Statements		
89	RIGHT\$	Extracts a character string comprising a specified number of digits from the right end of a specified character string.	-	Functions		
90	RIGHTY	Sets the hand system of a specified robot to "Right."	0	Command Statements		
91	RSHIFT	Shifts a value to the right by the specified number of bits. (↔LSHIFT)	-	Functions		

S			Online	Туре
3				
92	SELECT CASE to END SELECT	Allows control flow to branch according to conditions.	×	Command Statements
93	SEND	Sends a file.	0	Command Statements
94	SERVO	Controls the servo ON/OFF of a specified axis or all axes of a specified robot.	0	Command Statements
95	SET	Turns the bit at the specified output port ON.	Δ	Command Statements
96	SHARED	Enables reference with a sub-procedure without transferring a variable.	X	Command Statements
97	SHIFT	Sets the shift coordinate for a specified robot by using the shift data specified by a shift variable.	0	Command Statements
98	SIN	Acquires the sine value for a specified value.	-	Functions
99	Sn	Defines the shift coordinates within the program.	0	Command Statements
100	SO	Outputs a specified value to the SO port.	0	Command Statements
101	SPEED	Changes the program movement speed of a specified robot.	0	Command Statements
102	SQR	Acquires the square root of a specified value.	-	Functions
103	START	Specifies the task number and priority ranking of a specified program, and starts that program.	0	Command Statements
104	STR\$	Converts a specified value to a character string $(\leftrightarrow VAL)$	-	Functions
105	SUB to END SUB	Defines a sub-procedure.	×	Command Statements
106	SUSPEND	Temporarily stops another task which is being executed.	×	Command Statements
107	SWI	Switches the program being executed, then begins execution from the first line.	×	Command Statements
Т				
108	TAN	Acquires the tangent value for a specified value.	_	Functions
109	TCOUNTER	Outputs count-up values at 10ms intervals starting from the point when the TCOUNTER variable is reset.	-	Functions
110	TIME\$	Acquires the current time as an "hh:mm:ss" format character string.	-	Functions
111	TIMER	Acquires the current time in seconds, counting from 12:00 midnight.	-	Functions
112	TO	Outputs a specified value to the TO port.	0	Command Statements
113	TOLE	Specifies/acquires the tolerance parameter of a specified robot.	0	Command Statements/ Functions
114	TORQUE	Specifies/acquires the maximum torque command value which can be set for a specified axis of a specified robot.	0	Command Statements/ Functions
٧				
115	VAL	Converts the numeric value of a specified character string to an actual numeric value. (←STR\$)	-	Functions
W				
116	WAIT	Waits until the conditions of the DI/DO conditional expression are met (with time-out).	×	Command Statements
117	WAIT ARM	Waits until the axis operation of a specified robot is completed.	X	Command Statements
118	WEIGHT	Specifies/acquires the tip weight parameter of a specified robot.	0	Command Statements/ Functions
119	WEND	Terminates the command block of the WHILE statement.	×	Command Statements
120	WHERE	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).	-	Functions
121	WHILE to WEND	Controls repeated operations.	×	Command Statements
122	WHRXY	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).	-	Functions
X				
123	XYTOJ	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. ( $\leftrightarrow$ JTOXY).	-	Functions

## **Function Specific**

## Program commands

## General commands

No.	Command	Function	Online	Туре
25	DIM	Declares the array variable name and the number of elements.	×	Command Statements
51	LET	Executes a specified assignment statement.	0	Command Statements
84	REM	Expresses a comment statement.	×	Command Statements

#### Arithmetic commands

No.	Command	Function	Online	Туре
1	ABS	Acquires the absolute value of a specified value.	-	Command Statements
9	ATN	Acquires the arctangent of the specified value.	-	Functions
9	ATN2	Acquires the arctangent of the specified X-Y coordinates.	-	Functions
15	cos	Acquires the cosine value of a specified value.	-	Functions
22	DEGRAD	Converts a specified value to radians (↔RADDEG).	-	Functions
26	DIST	Acquires the distance between 2 specified points.	-	Functions
46	INT	Acquires an integer for a specified value by truncating all decimal fractions.	-	Functions
54	LSHIFT	Shifts a value to the left by the specified number of bits. $(\leftrightarrow \text{RSHIFT})$	-	Functions
83	RADDEG	Converts a specified value to degrees. (↔DEGRAD)	-	Functions
91	RSHIFT	Shifts a value to the right by the specified number of bits. $(\leftrightarrow LSHIFT)$	-	Functions
98	SIN	Acquires the sine value for a specified value.	-	Functions
102	SQR	Acquires the square root of a specified value.	-	Functions
108	TAN	Acquires the tangent value for a specified value.	-	Functions

#### Date / time

No.	Command	Function	Online	Туре
19	DATE \$	Acquires the date as a "yy/mm/dd" format character string.	-	Functions
109	TCOUNTER	Outputs count-up values at 10ms intervals starting from the point when the TCOUNTER variable is reset.	-	Functions
110	TIME \$	Acquires the current time as an "hh:mm:ss" format character string.	-	Functions
111	TIMER	Acquires the current time in seconds, counting from 12:00 midnight.	-	Functions

## Character string operation

No.	Command	Function	Online	Туре
14	CHR\$	Acquires a character with the specified character code.	-	Functions
48	LEFT \$	Extracts a character string comprising a specified number of digits from the left end of a specified character string.	-	Functions
50	LEN	Acquires the length (number of bytes) of a specified character string.	-	Functions
56	MID \$	Extracts a character string of a desired length from a specified character string.	-	Functions
66	ORD	Acquires the character code of the first character in a specified character string.	-	Functions
89	RIGHT \$	Extracts a character string comprising a specified number of digits from the right end of a specified character string.	-	Functions
104	STR\$	Converts a specified value to a character string (↔VAL)	-	Functions
115	VAL	Converts the numeric value of a specified character string to an actual numeric value. (←STR\$)	-	Functions

## Point, coordinates, shift coordinates

No.	Command	Function	Online	Туре
12	CHANGE	Switches the hand of a specified robot.	0	Command Statements
41	HAND	Defines the hand of a specified robot.	0	Command Statements
47	JTOXY	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (→XYTOJ)	-	Functions
49	LEFTY	Sets the hand system of a specified robot to "Left."	0	Command Statements
53	LOCx	Specifies/acquires point data for a specified axis or shift data for a specified element.	-	Command Statements/ Functions
73	Pn	Defines points within a program.	0	Command Statements
74	PPNT	Creates point data specified by a pallet definition number and pallet position number.	-	Functions
90	RIGHTY	Sets the hand system of a specified robot to "Right."	0	Command Statements
99	Sn	Defines the shift coordinates in the program.	0	Command Statements
97	SHIFT	Sets the shift coordinate for a specified robot by using the shift data specified by a shift variable.	0	Command Statements
123	XYTOJ	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (←JTOXY).	-	Functions

## Branching commands

No.	Command	Function	Online	Туре
33	EXIT FOR	Terminates the FOR to NEXT statement loop.	×	Command Statements
36	FOR to NEXT	Controls repetitive operations. Executes the FOR to NEXT statement repeatedly until a specified value is exceeded.	×	Command Statements
37	GOSUB to RETURN	Jumps to a subroutine with the label specified by a GOSUB statement, and executes that subroutine.	×	Command Statements
38	GOTO	Unconditionally jumps to the line specified by a label.	×	Command Statements
44	IF	Allows control flow to branch according to conditions.	×	Command Statements
63	ON to GOSUB	Jumps to a subroutine with labels specified by a GOSUB statement in accordance with the conditions, and executes that subroutine.	×	Command Statements
64	ON to GOTO	Jumps to label-specified lines in accordance with the conditions.	×	Command Statements
92	SELECT CASE to END SELECT	Allows control flow to branch according to conditions.	×	Command Statements
121	WHILE to WEND	Controls repeated operations.	×	Command Statements

## Error control

No.	Command	Function	Online	Туре
62	ON ERROR GOTO	If an error occurs during program execution, this command allows the program to jump to the error processing routine specified by the label without stopping the program, or it stops the program and displays the error message.	×	Command Statements
87	RESUME	Resumes program execution after error recovery processing.	×	Command Statements
32	ERL	Gives the line No. where an error occurred.	-	Functions
32	ERR	Gives the error code number of an error which has occurred.	-	Functions

## Program & task control

## Program control

No.	Command	Function	Online	Туре
11	CALL	Calls a sub-procedure.	×	Command Statements
39	HALT	Stops the program and performs a reset.	×	Command Statements
40	HALTALL	Stops all programs, resets task 1, and terminates all other tasks.	×	Command Statements
42	HOLD	Temporarily stops the program.	×	Command Statements
43	HOLDALL	Temporarily stops all programs.	×	Command Statements
107	SWI	Switches the program being executed, performs compiling, then begins execution from the first line.	×	Command Statements

#### Task control

No.	Command	Function	Online	Туре
13	CHGPRI	Changes the priority ranking of a specified task.	-	Command Statements
18	CUT	Terminates a task currently being executed or temporarily stopped.	0	Command Statements
35	EXIT TASK	Terminates its own task which is in progress.	×	Command Statements
82	PUSH	Executes a pushing operation in the axis unit.		Command Statements
86	RESTART	Restarts another task during a temporary stop.	0	Command Statements
103	START	Specifies the task number and priority ranking of a specified task, and starts that task.	0	Command Statements
106	SUSPEND	Temporarily stops another task which is being executed.	X	Command Statements

## Robot control

## Robot operations

No.	Command	Function	Online	Туре
12	CHANGE	Switches the hand of a specified robot.	0	Command Statements
28	DRIVE	Moves a specified axis of a specified robot to an absolute position.	0	Command Statements
29	DRIVEI	Moves a specified axis of a specified robot to a relative position.	0	Command Statements
41	HAND	Defines the hand of a specified robot.	0	Command Statements
49	LEFTY	Sets the hand system of a specified robot to "Left."	0	Command Statements
58	MOTOR	Controls the motor power status.	0	Command Statements
59	MOVE	Performs absolute movement of all axes of a specified robot.	0	Command Statements
60	MOVEI	Performs relative movement of all axes of a specified robot.	0	Command Statements
68	ORIGIN	Performs a return-to-origin.	0	Command Statements
72	PMOVE	Executes the pallet movement command of a specified robot.	0	Command Statements
90	RIGHTY	Sets the hand system of a specified robot to "Right."	0	Command Statements
94	SERVO	Controls the servo ON/OFF of a specified axis or all axes of a specified robot.	0	Command Statements

## Status acquisition

No.	Command	Function	Online	Туре
2	ABSRPOS	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)	-	Command Statements/ Functions
5	ARMCND	Acquires the current arm status of a specified robot.	-	Functions
6	ARMSEL	Acquires the current "hand system" setting of a specified robot.	-	Functions
7	ARMTYP	Acquires the "hand system" setting of a specified robot.	_	Functions
16	CURTQST	Acquires the current torque against the rated torque of a specified axis.	-	Functions
55	MCHREF	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.	-	Functions
79	PSHRSLT	Acquires the status at the end of the PUSH statement.	-	Functions
80	PSHSPD	Specifies/acquires the pushing movement speed parameter.	0	Command Statements/ Functions
81	PSHTIME	Specifies/acquires the pushing time parameter.	0	Command Statements/ Functions
117	WAIT ARM	Waits until the axis operation of a specified robot is completed.	X	Command Statements
120	WHERE	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).	-	Functions
122	WHRXY	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).	-	Functions

## Status change

No.	Command	Function	Online	Туре
3	ACCEL	Specifies/acquires the acceleration coefficient parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP1	Specifies/acquires the arch position 1 parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP2	Specifies/acquires the arch position 2 parameter of a specified robot.	0	Command Statements/ Functions

No.	Command	Function	Online	Туре
8	ASPEED	Specifies/acquires the AUTO movement speed of a specified robot.	0	Command Statements/ Functions
10	AXWGHT	Specifies/acquires the axis tip weight parameter of a specified robot.	0	Command Statements/ Functions
20	DECEL	Specifies/acquires the deceleration rate parameter of a specified robot.	0	Command Statements/ Functions
67	ORGORD	Specifies/acquires the axis sequence parameter for performing return-to-origin and an absolute search operation in a specified robot.	0	Command Statements/ Functions
70	OUTPOS	Specifies/acquires the OUT enable position parameter of a specified robot.	0	Command Statements/ Functions
71	PDEF	Defines the pallet used to execute pallet movement commands.	0	Command Statements
76	PSHFRC	Specifies/acquires the pushing thrust parameter.	0	Command Statements/ Functions
77	PSHJGSP	Specifies/acquires the pushing check speed threshold parameter.	0	Command Statements/ Functions
78	PSHMTD	Specifies/acquires the pushing method parameter.	0	Command Statements/ Functions
101	SPEED	Changes the program movement speed of a specified robot.	0	Command Statements
113	TOLE	Specifies/acquires the tolerance parameter of a specified robot.	0	Command Statements/ Functions
118	WEIGHT	Specifies/acquires the tip weight parameter of a specified robot.	0	Command Statements/ Functions

## Input/output & communication control

## Input/output control

No.	Command	Function	Online	Туре
23	DELAY	Waits for the specified period (units: ms).	×	Command Statements
27	DO	Outputs a specified value to the DO port.	0	Command Statements
52	LO	Outputs a specified value to the LO port to enable/disable axis movement.	0	Command Statements
57	МО	Outputs a specified value to the MO port.	0	Command Statements
69	OUT	Turns ON the bits of the specified output ports and the command statement ends.	×	Command Statements
85	RESET	Turns the bit of a specified output port OFF.	0	Command Statements
95	SET	Turns the bit at the specified output port ON.	Δ	Command Statements
100	so	Outputs a specified value to the SO port.	0	Command Statements
112	ТО	Outputs a specified value to the TO port.	0	Command Statements
116	WAIT	Waits until the conditions of the DI/DO conditional expression are met (with time-out).	×	Command Statements

## Communication control

No.	Command	Function	Online	Туре
65	ONLINE	Sets the specified communication port to the "online" mode.	0	Command Statements
61	OFFLINE	Sets a specified communication port to the "offline" mode.	0	Command Statements
93	SEND	Sends a file.	0	Command Statements

# Functions: in alphabetic order

Function	Туре	Function	
ABS	Arithmetic function	Acquires the absolute value of a specified value.	
ABSRPOS	Arithmetic function	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)	
ACCEL	Arithmetic function	Acquires the acceleration coefficient parameter of a specified robot.	
ARCHP1	Arithmetic function	Acquires the arch position 1 parameter of a specified robot.	
ARCHP2	Arithmetic function	Acquires the arch position 2 parameter of a specified robot.	
ARMCND	Arithmetic function	Acquires the current arm status of a specified robot.	
ARMSEL	Arithmetic function	Acquires the current "hand system" setting of a specified robot.	
ARMTYP	Arithmetic function	Acquires the "hand system" setting of a specified robot.	
ASPEED	Arithmetic function	Sets the automatic movement speed.	
ATN	Arithmetic function	Acquires the arctangent of the specified value.	
ATN2	Arithmetic function	Acquires the arctangent of the specified X-Y coordinates.	
AXWGHT	Arithmetic function	Acquires the axis tip weight parameter of a specified robot.	
CHR\$	Character string function	Acquires a character with the specified character code.	
cos	Arithmetic function	Acquires the cosine value of a specified value.	
CURTQST	Arithmetic function	Acquires the current torque against the rated torque of a specified axis.	
CURTRQ	Arithmetic function	Acquires the current torque value of the specified axis of a specified robot.	
DATE\$	Character string function	Acquires the date as a "yy/mm/dd" format character string.	
DECEL	Arithmetic function	Acquires the deceleration rate parameter of a specified robot.	
DEGRAD	Arithmetic function	Converts a specified value to radians (→RADDEG).	
DIST	Arithmetic function	Acquires the distance between 2 specified points.	
ERL	Arithmetic function	Gives the line No. where an error occurred.	
ERR	Arithmetic function	Gives the error code number of an error which has occurred.	
INT	Arithmetic function	Acquires an integer for a specified value by truncating all decimal fractions.	
JTOXY	Point function	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (↔XYTOJ)	
LEFT\$	Character string function	Extracts a character string comprising a specified number of digits from the left end of a specified character string.	
LEN	Arithmetic function	Acquires the length (number of bytes) of a specified character string.	
LOCx	Point function	Specifies/acquires point data for a specified axis or shift data for a specified element.	
LSHIFT	Arithmetic function	Shifts a value to the left by the specified number of bits. (→RSHIFT)	
	ABS ABSRPOS  ACCEL ARCHP1 ARCHP2 ARMCND ARMSEL ARMTYP ASPEED ATN ATN2 AXWGHT  CHR\$  COS CURTQST CURTRQ  DATE\$  DECEL DEGRAD DIST  ERL ERR  INT  JTOXY  LEFT\$ LEN LOCx	ABS Arithmetic function ABSRPOS Arithmetic function ACCEL Arithmetic function ARCHP1 Arithmetic function ARCHP2 Arithmetic function ARMCND Arithmetic function ARMSEL Arithmetic function ARMTYP Arithmetic function ATN Arithmetic function ATN Arithmetic function ATN Arithmetic function ATNA Arithmetic function CURTQ Arithmetic function CURTQST Arithmetic function CURTRQ Arithmetic function  DATE\$ Character string function CURTRQ Arithmetic function  DECEL Arithmetic function DECEL Arithmetic function DIST Arithmetic function  ERL Arithmetic function  ERR Arithmetic function  LER Arithmetic function  LER Arithmetic function  Arithmetic function  CURTRQ Arithmetic function  CURTRQ Arithmetic function  DATE\$ Character string function  ERL Arithmetic function  ERR Arithmetic function  LERL Arithmetic function  Arithmetic function  CURTRQ Arithmetic function  ERR Arithmetic function	

No.	Function	Туре	Function
M			
55	MCHREF	Arithmetic function	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.
56	MID\$	Character string function	Extracts a character string of a desired length from a specified character string.
0			
66	ORD	Arithmetic function	Acquires the character code of the first character in a specified character string.
67	ORGORD	Arithmetic function	Acquires the axis sequence parameter for performing return-to- origin and an absolute search operation of a specified robot.
70	OUTPOS	Arithmetic function	Acquires the OUT enable position parameter of a specified robot.
P			
74	PPNT	Point function	Creates point data specified by a pallet definition number and pallet position number.
76	PSHFRC	Arithmetic function	Specifies/acquires a pushing thrust parameter.
77	PSHJGSP	Arithmetic function	Specifies/acquires a pushing detection speed threshold parameter.
78	PSHMTD	Arithmetic function	Specifies/acquires a pushing type parameter.
79	PSHRSLT	Arithmetic function	Acquires the status when PUSH statement ends.
80	PSHSPD	Arithmetic function	Specifies/acquires the pushing movement speed parameter.
81	PSHTIME	Arithmetic function	Acquires the status at the end of the PUSH statement.
R			
83	RADDEG	Arithmetic function	Converts a specified value to degrees. (↔DEGRAD)
89	RIGHT\$	Character string function	Extracts a character string comprising a specified number of digits from the right end of a specified character string.
91	RSHIFT	Arithmetic function	Shifts a value to the right by the specified number of bits. $(\leftrightarrow \text{LSHIFT})$
S			
98	SIN	Arithmetic function	Acquires the sine value for a specified value.
102	SQR	Arithmetic function	Acquires the square root of a specified value.
104	STR\$	Character string function	Converts a specified value to a character string (↔VAL)
T			
108	TAN	Arithmetic function	Acquires the tangent value for a specified value.
109	TCOUNTER	Arithmetic function	Outputs count-up values at 10ms intervals starting from the point when the TCOUNTER variable is reset.
110	TIME\$	Character string function	Acquires the current time as an "hh:mm:ss" format character string.
111	TIMER	Arithmetic function	Acquires the current time in seconds, counting from 12:00 midnight.
113	TOLE	Arithmetic function	Acquires the tolerance parameter of a specified robot.
114	TORQUE	Arithmetic function	Acquires the maximum torque command value which can be set for a specified axis of a specified robot.
٧			
115	VAL	Arithmetic function	Converts the numeric value of a specified character string to an actual numeric value. (←STR\$)
W			
118	WEIGHT	Arithmetic function	Acquires the tip weight parameter of a specified robot.
120	WHERE	Point function	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).

No.	Function	Туре	Function
122	WHRXY	Point function	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).
X			
123	XYTOJ	Point function	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (←JTOXY).

# Functions: operation-specific

#### Point related functions

No.	Function name	Function
47	JTOXY	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (↔XYTOJ)
53	LOCx	Acquires point data for a specified axis or shift data for a specified element.
74	PPNT	Creates point data specified by a pallet definition number and pallet position number.
120	WHERE	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).
122	WHRXY	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).
123	XYTOJ	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (←JTOXY).

## Parameter related functions

No.	Function name	Function
2	ABSRPOS	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)
3	ACCEL	Acquires the acceleration coefficient parameter of a specified robot.
4	ARCHP1	Acquires the arch position 1 parameter of a specified robot.
4	ARCHP2	Acquires the arch position 2 parameter of a specified robot.
5	ARMCND	Acquires the current arm status of a specified robot.
6	ARMSEL	Acquires the current "hand system" setting of a specified robot.
7	ARMTYP	Acquires the "hand system" setting of a specified robot.
10	AXWGHT	Acquires the axis tip weight parameter of a specified robot.
16	CURTQST	Acquires the current torque against the rated torque of a specified axis.
17	CURTRQ	Acquires the current torque value of the specified axis of a specified robot.
20	DECEL	Acquires the deceleration rate parameter of a specified robot.
50	LEN	Acquires the length (number of bytes) of a specified character string.
55	MCHREF	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.
66	ORD	Acquires the character code of the first character in a specified character string.
67	ORGORD	Acquires the axis sequence parameter for performing return-to-origin and an absolute search operation of a specified robot.
70	OUTPOS	Acquires the OUT enable position parameter of a specified robot.
79	PSHRSLT	Acquires the status at the end of the PUSH statement.
113	TOLE	Acquires the tolerance parameter of a specified robot.
114	TORQUE	Acquires the maximum torque command value which can be set for a specified axis of a specified robot.
118	WEIGHT	Acquires the tip weight parameter of a specified robot.

#### Numeric calculation related functions

No.	Function name	Function
1	ABS	Acquires the absolute value of a specified value.
9	ATN	Acquires the arctangent of the specified value.
9	ATN2	Acquires the arctangent of the specified X-Y coordinates.
15	cos	Acquires the cosine value of a specified value.
22	DEGRAD	Converts a specified value to radians (↔RADDEG).
26	DIST	Acquires the distance between 2 specified points.
46	INT	Acquires an integer for a specified value by truncating all decimal fractions.
54	LSHIFT	Shifts a value to the left by the specified number of bits. (↔RSHIFT)
83	RADDEG	Converts a specified value to degrees. (↔DEGRAD)
91	RSHIFT	Shifts a value to the right by the specified number of bits. (→LSHIFT)
98	SIN	Acquires the sine value for a specified value.
102	SQR	Acquires the square root of a specified value.
108	TAN	Acquires the tangent value for a specified value.
115	VAL	Converts the numeric value of a specified character string to an actual numeric value. (→STR\$)

## Character string calculation related functions

No.	Function name	Function
14	CHR\$	Acquires a character with the specified character code.
19	DATE \$	Acquires the date as a "yy/mm/dd" format character string.
48	LEFT \$	Extracts a character string comprising a specified number of digits from the left end of a specified character string.
56	MID \$	Extracts a character string of a desired length from a specified character string.
89	RIGHT \$	Extracts a character string comprising a specified number of digits from the right end of a specified character string.
104	STR\$	Converts a specified value to a character string (↔VAL)

#### Parameter related functions

No.	Function name	Function
32	ERL	Gives the line No. where an error occurred.
32	ERR	Gives the error code number of an error which has occurred.
109	TCOUNTER	Outputs count-up values at 1ms intervals starting from the point when the TCOUNTER variable is reset.
110	TIME \$	Acquires the current time as an "hh:mm:ss" format character string.
111	TIMER	Acquires the current time in seconds, counting from 12:00 midnight.

## Format

ABS (<expression>)

Explanation Returns a value specified by an <expression> as an absolute value.

#### SAMPLE

A=ABS(-326.55) ..... The absolute value of -362.54  $(=362.54) \ \mbox{is assigned to}$  variable A.

A

В

D

E

F

G

Н

J

λA

#### **Format**

ABSRPOS [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number>......1 to 6

Explanation The machine reference value for a specified by the <axis number> of the robot specified by the <robot number> is acquired (unit: %). The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> This function is valid only for axes where the return-to-origin method is set as "mark method". It is not valid at axes where the return-to-origin method is set as "sensor" or "stroke end".

 At axes where return-to-origin method is set to "mark" method, absolute reset is possible when the machine reference value is in a 44 to 56% range.

#### SAMPLE

A=ABSRPOS(4) ..... The machine reference value for axis 4 of robot assigned to variable A.

D

#### **ACCEL**

Specifies/acquires the acceleration coefficient parameter

#### **Format**

- 1. ACCEL [<robot number>] <expression>
- 2. ACCEL [<robot number>] (<axis number>) =<expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......1 to 100 (units: %)

Explanation Directly changes the acceleration coefficient parameter of the robot axis specified by the <robot number> to the value specified by the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> In format 1, the change occurs at all axes specified with a specified robot. In format 2, the change occurs at the axis specified in <axis number>.



- \_\_\_\_\_\_ • If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and command execution is stopped.
  - · Changes the value which has been set at an operation terminal such as a pendant box. Program declared values have priority.

#### **Functions**

#### **Format**

ACCEL [<robot number>] (<axis number>)

**Values** 

<robot number>......1 to 4 <axis number>.....1 to 6

Explanation The acceleration parameter value is acquired for the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

..... The acceleration coefficient of

#### SAMPLE

A = 50

all axes of robot 1 becomes 50%. ACCEL(3)=100 ·····················Only axis 3 of robot 1 becomes 100%. 'CYCLE WITH INCREASING ACCELERATION FOR A=10 TO 100 STEP 10... The acceleration coefficient parameter is increased from 10% to 100% in 10% increments. ACCEL A MOVE P, P0 MOVE P, P1 A=ACCEL(3) ..... The acceleration coefficient parameter of axis 3 of robot 1 is assigned to variable A. HALT "END TEST"

Specifies/acquires the acceleration coefficient parameter

#### **Format**

ARCHP1 / ARCHP2

- 1. ARCHP1 [<robot number>] <expression>
- 2. ARCHP1 [<robot number>] (<axis number>) =<expression>

#### **Format**

- 1. ARCHP2 [<robot number>] <expression>
- 2. ARCHP2 [<robot number>] (<axis number>) =<expression>

#### (Values)

```
<robot number>......1 to 4
<axis number>......1 to 6
<expression>......1 to 6144000 (Unit: pulses)
```

Explanation ARCHP1 corresponds to the arch position parameter; ARCHP2 corresponds to the arch position 2 parameter, respectively. Changes the parameter's arch position to the value indicated in the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

In format 1, the change occurs at all axes specified with a specified robot.

In format 2, the change occurs at the arch position parameter for the axis specified in <axis number> to the value specified in <expression>.



• If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and command execution is stopped.

#### Functions

#### **Format**

ARCHP1 [<robot number>] (<axis number>)

#### **Format**

ARCHP2 [<robot number>] (<axis number>)



<robot number>......1 to 4 <axis number>......1 to 6

Explanation ARCHP1 corresponds to the arch position parameter; ARCHP2 corresponds to the arch position 2 parameter, respectively.

Acquires the arch position parameter value of the axis specified at <axis number>.

The <robot number> can be omitted. If it is omitted, robot 1 is specified.

```
SAMPLE
DIM SAV (3)
DIM SAV2 (3)
GOSUB *SAVE ARCH
FOR A=1000 TO 10000 STEP 1000
   GOSUB *CHANGE ARCH
   MOVE P, P0, A3=0
   DO3 (0) =1 · · · · · Chuck CLOSE
   MOVE P, P1, A3=0
   DO3 (0) = 0 ..... Chuck OPEN
NEXT A
GOSUB *RESTORE ARCH
HALT
*CHANGE ARCH:
FOR B=1 TO 4
   ARCHP1 (B) =A
   ARCHP2 (B) =A
NEXT B
RETURN
*SAVE ARCH:
FOR B=1 TO 4
   SAV (B-1) =ARCHP1 (B) \cdots The arch position parameters
                           ARCHP1(1) to (4) are assigned to
                           array variables SAV(0) to (3).
   SAV2 (B-1) = ARCHP2 (B)
NEXT B
RETURN
*RESTORE ARCH:
FOR B=1 TO 4
   ARCHP1 (B) =SAV (B-1)
   ARCHP2 (B) = SAV2 (B-1)
NEXT B
RETURN
```

A

В

D

E

F

G

П

J

N.

L

M

#### **Format**

ARMCND [<robot number>]

Values

<robot number>......1 to 4

Explanation This function acquires the current arm status of the SCARA robot. The robot to acquire an arm status is specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

The arm status is "2" for a left-handed system and "1" for a right-handed system.

This function is enabled only when a SCARA robot is used.

#### SAMPLE

```
A=ARMCND ..... The current
                                    arm
                                         status
                      of robot 1 is assigned to
                      variable A.
IF A=0 THEN ..... Right-handed system status.
MOVE P, P100, Z=0
       ..... Left-handed system status.
ELSE
MOVE P, P200, Z=0
ENDIF
```

Sets/acquires the current hand system selection.

#### **Format**

ARMSEL [<robot number>] <expression>

Values

<robot number>......1 to 4

<expression>.....1: right hand system; 2: left hand system

Explanation This function sets the current hand system selection of the SCARA robot. A robot to set a hand system is specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

This function is enabled only when a SCARA robot is used.

SAMPLE

ARMSEL[2] 2 ..... Sets the left-handed system for the hand system selection of the robot 2.

#### **Functions**

#### **Format**

ARMSEL [<robot number>]

**Values** 

<robot number>......1 to 4

Explanation This function acquires the hand system currently selected for the SCARA robot. The robot to acquire a hand system is specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> The arm type is "2" for a left-handed system, and "1" for a right-handed system. This function is enabled only when a SCARA robot is used.

SAMPLE

A=ARMSEL ..... The arm type value of robot 1 is assigned.

IF A=1 THEN ····· The arm type is a right-handed system.

MOVE P, P100, Z=0

...... The arm type is a left-handed system.

MOVE P, P200, Z=0

ENDIF

#### ARMTYP

Sets/acquires the hand system selection during program reset.

#### **Format**

ARMTYP [<robot number>] <expression>

(Values)

<robot number>......1 to 4

<expression>......1: right hand system; 2: left hand system

Explanation This function sets the hand system at program reset of the SCARA robot. A robot to set a hand system selection is specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

This function is enabled only when a SCARA robot is used.

#### SAMPLE

ARMTYP[2] 2 ..... Sets the left-handed system for the hand system of the robot 2.

#### Functions

#### **Format**

ARMTYP [<robot number>]

**Values** 

<robot number>......1 to 4

Explanation This function provides the hand system at program reset of the SCARA robot. The robot to acquire a hand system is specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> The arm type is "2" for a left-handed system, and "1" for a right-handed system. This function is enabled only when a SCARA robot is used.

#### SAMPLE

..... The arm type value of robot 1 A=ARMTYP is assigned. IF A=1 THEN ..... The arm type is a right-handed system. MOVE P, P100, Z=0

ELSE  $\cdots\cdots$  The arm type is a left-handed system.

MOVE P, P200, Z=0

ENDIF

HALTALL ..... Program reset

7-22 Chapter 7 Robot Language Lists

Sets/acquires the AUTO movement speed of a specified robot.

#### **Format**

ASPEED [<robot number>] <expression>

Values

<robot number>......1 to 4

<expression>......1 to 100 (units: %)

 Automatic movement speed

Specified by programming box operation or by the ASPEED command.

• Program movement speed

Specified by SPEED commands or MOVE, DRIVE speed settings.

Explanation Directly changes the automatic movement speed of the robot specified by the <robot number> to the value indicated in the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> This speed change applies to all the robot axes and auxiliary axes. The operation speed is determined by the product of the automatic movement speed (specified by programming box operation and by the ASPEED command), and the program movement speed (specified by SPEED command, etc.).

Operation speed = automatic movement speed x program movement speed.

Example:

80% Automatic movement speed Program movement speed 50% Movement speed =  $40\% (80\% \times 50\%)$ 

#### **Functions**

#### **Format**

ASPEED [<robot number>]

Values

<robot number>......1 to 4

Explanation Acquire the automatic movement speed value of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

SAMPLE

SPEED 70

ASPEED 100

MOVE P,P0 ..... Movement from the current position to P0 occurs at 70% speed (=100 \* 70).

ASPEED 50

MOVE P,P1 ..... Movement from the current position to P1 occurs at 35% speed (=50 \* 70).

MOVE P, P2, S=10 ..... Movement from the current

position to P2 occurs at 5%

speed (=50 \* 10).

HALT

Related commands

**SPEED** 

D

#### **Format**

ATN / ATN2

ATN (<expression>)

#### **Format**

ATN2 (<expression 1>) (<expression 2>)

Explanation ATN: Acquires the arctangent values of the specified <expression> values. The

acquired values are radians within the following range:  $-\pi$  / 2 to  $+\pi$  / 2

ATN2: Acquires the arctangent values of the specified <expression 1> and

<expression 2> X-Y coordinates. The acquired values are radians within

the following range:  $-\pi$  to  $+\pi$ 

#### SAMPLE

A(0)=A\*ATN(Y/X) ...... The product of the expression (Y/X) arctangent value and variable A is assigned to

array A (0).

A(0) = ATN(0.5) ..... The 0.5 arctangent value is assigned to array A(0).

A(0)=ATN2(B,C)-D ..... The difference between the X-Y coordinates (B,C) arctangent value and variable D is

assigned to array A (0).

A(1)=RADDEG(ATN2(B,C)) ····· The X-Y coordinates (B,C)

arctangent value is converted to degrees, and is then

assigned to array A (1).

Related commands

COS, DEGRAD, RADDEG, SIN, TAN

В

C

ע

E

Е

G

Е

Ш

- -

L

Sets/acquires the axis tip weight

#### **Format**

AXWGHT [<robot number>] (<axis number>) =<expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6

<expression>......Varies according to the specified robot.

Explanation Directly changes the axis tip weight parameter for the axis specified by the <axis number> among the robot axes specified by the <robot number> to the <expression> value. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

This statement is valid in systems with "MULTI" axes and auxiliary axes (the robot type and auxiliary axes are factory set prior to shipment).

#### **Functions**

#### **Format**

AXWGHT [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the axis tip weight parameter value for the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

This statement is valid in systems with "MULTI" axes and auxiliary axes.

#### SAMPLE

A=5B=0

C=AXWGHT(1) ......Axis tip weight value is acquired (the current value is saved to variable C).

AXWGHT(1) = ADRIVE(1,P0)

AXWGHT(1) = B

DRIVE(1,P1)

AXWGHT(1)=C ..... The axis tip weight value is set again.

HALT

Related commands

**WEIGHT** 

D

## CALL

Calls a sub-procedure



#### **NOTE**

- When a value is passed on to a sub-procedure, the original value of the actual argument will not be changed even if it is changed in the subprocedure.
- When a reference is passed on to a subprocedure, the original value of the actual argument will also be changed if it is changed in the sub-procedure.
- For details, see Chapter 3 "8 Value Pass-Along & Reference Pass-Along".



#### **Format**

```
CALL <label> [(<actual argument> [, <actual argument>...])]
```

Explanation This statement calls up sub-procedures defined by the SUB to END SUB statements. The <label> specifies the same name as that defined by the SUB statement.

- 1. When a constant or expression is specified as an actual argument, its value is passed on to the sub-procedure.
- 2. When a variable or array element is specified as an actual argument, its value is passed on to the sub-procedure. It will be passed on as a reference if "REF" is added at the head of the actual argument.
- 3. When an entire array (array name followed by parentheses) is specified as an actual argument, it is passed along as a reference.

.....

- CALL statements can be used up to 120 times in succession. Note that this number is reduced if commands which use stacks such as an FOR statement or GOSUB statement are used, or depending on the use status of identifiers.
- Always use the END SUB or EXT SIB statement to end a sub-procedure which has been called with the CALL statement. If another statement such as GOTO is used to jump out of the subroutine, a "5.12: Stack overflow" error, etc., may occur.

```
SAMPLE 1
X%=4
Y%=5
CALL *COMPARE ( REF X%, REF Y% )
HALT
 SUB ROUTINE:
                COMPARE
SUB *COMPARE ( A%,
   IF A% < B% THEN
      TEMP%=A%
      A%=B%
      B%=TEMP%
   ENDIF
END SUB
```

```
SAMPLE 2
I = 1
CALL
      *TEST(I)
HALT
' SUB ROUTINE:
                TEST
SUB *TEST
   X = X + 1
   IF X < 15 THEN
      CALL *TEST(X)
   ENDIF
END SUB
```

Related commands

SUB, END SUB, CALL, EXIT SUB, SHARED

#### CHANGE Switches the hand

Format		
CHANGE [ <robot number="">]</robot>	Hn OFF	

**Explanation** CHANGE is used to switch the robot hand specified by the <robot number>. If OFF is specified, the hand setting is not enabled. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

Before hand switching can occur, the hands must be defined at the HAND statement. For details, see section "41 HAND". If hand data defined with another robot specified is specified, "Hand data mismatch error" occurs.

SAMPLE				
HAND H1=	0	150.0	0.0	
HAND H2=	-5000	20.00	0.0	
P1=150.00	300.00	0.00 0.00	0 0.00 0.00	
CHANGE H2	• • • • • • • • • • • • • • • • • • • •		· Changes to hand 2.	
MOVE P, P1	• • • • • • • • • • • • • • • • • • • •		$\cdot \cdot$ Moves the hand 2 tip to P1 (1)	
CHANGE H1	• • • • • • • • • • • • • • • • • • • •		$\cdot \cdot$ Changes to hand 1.	
MOVE P, P1	• • • • • • • • • • • • • • • • • • • •		$\cdot \cdot$ Moves the hand 1 tip to P1 (2)	
HALT				

A

В

C

D

E

F

G

Ш

M

#### CHGPRI

Changes the priority ranking of a specified task

#### **Format** CHGPRI Tn ,p "< "<pre>cprogram name" >" PGm

Values

m: Program number ......0 to 99 n: Task No ......1 to 16 p: Task priority ranking .......1 to 64

**Explanation** Directly changes the priority ranking of the specified task ("n") to "p".

The smaller the priority number, the higher the priority (high priority: 1 ⇔ low priority: 64).

When a READY status occurs at a task with higher priority, all tasks with lower priority also remain in a READY status.

```
SAMPLE
START <SUB PGM>, T2, 33
*ST:
   MOVE P, P0, P1
   IF DI(20) = 1 THEN
      CHGPRI T2,32
   ELSE
      CHGPRI T2,33
   ENDIF
GOTO *ST
HALT
Program name: SUB PGM
*SUBPGM:
' SUBTASK ROUTINE
*SUBTASK:
   IF LOC3 (WHERE) > 10000 THEN
      DO(20) = 1
      GOTO *SUBPGM
   ENDIF
   DO(20) = 0
GOTO *SUBPGM
EXIT TASK
```

Related commands

CUT, EXIT TASK, RESTART, SUSPEND, START

Acquires a character with the specified character code

Format

CHR\$ (<expression>)

Values

<expression>......0 to 255

Explanation Acquires a character with the specified character code. An error occurs if the <expression> value is outside the 0 to 255 range.

SAMPLE

A\$=CHR\$(65) ····· "A" is assigned to A\$.

Related commands

ORD

B

C

П

В

G

Н

J

COS

#### **Format**

COS (<expression>)

Values

<expression>......Angle (units: radians)

**Explanation** Acquires a cosine value for the <expression> value.

#### SAMPLE

A(0) = B \* COS(C) ...... The product of the C42 variable's cosine value and variable B is assigned to array A (0). A(1) = COS(DEGRAD(20)) ..... The 20.0 ° cosine value is

A(1)=COS(DEGRAD(20)) ······· The 20.0 ° cosine value is assigned to array A (1).

Related commands

ATN, DEGRAD, RADDEG, SIN, TAN

A

В

C

D

E

F

G

Н

I

M

Acquires the current torque against the rated torque of a specified axis

**Format** 

CURTQST [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the current torque value (-1000 to 1000) against the rated torque of the axis specified by the <axis number> of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

SAMPLE

A = CURTQST(3) ..... The current torque value against the rated torque of the axis 3 of robot 1 is assigned to variable A.

#### CURTRQ

Acquires the current torque value of the specified axis

# -

#### NOTE

 If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and command execution is stopped.

#### **Format**

CURTRQ [<robot number>] (<expression>)

 Values
 <robot number>......1 to 4

 <expression>......1 to 6

Explanation Acquires the current torque value (-100 to 100) of the axis specified by the <expression> among the robot axes specified by the <robot number> is acquired.

The cropot number> can be omitted. If it is omitted, robot 1 is specified.

The current torque value is expressed as a paraentees of the maximum to

The current torque value is expressed as a percentage of the maximum torque command value. Plus/minus signs indicate the direction.

#### SAMPLE

A = CURTRQ(3) ..... The current torque value of the axis 3 of robot 1 is assigned to variable A.

Terminates another task which is currently being executed

**Format** 

CUT Tn "< "<pre>"< name</pre>" >"

Values

m: Program number .....0 to 99 n: Task No ......1 to 16

Explanation Directly terminates another task which is currently being executed or which is temporarily stopped. A task can be specified by the name or the number of a program in execution.

This statement cannot terminate its own task.

MEMO

• If a task (program) not active is specified for the execution, an error occurs.

```
SAMPLE
```

```
' TASK1 ROUTINE
*ST:
   MO(20) = 0
   START <SUB PGM>, T2
   MOVE P, P0
   MOVE P, P1
   WAIT MO(20) = 1
   CUT T2
GOTO *ST
HALT
Program name:SUB_PGM
*SUBPGM:
' TASK2 ROUTINE
*SUBTASK2:
   P100=JTOXY (WHERE)
   IF LOC3(P100) >= 100.0 THEN
      MO(20) = 1
   ELSE
      DELAY 100
   ENDIF
GOTO *SUBPGM
EXIT TASK
```

Related commands

EXIT TASK, CUT, RESTART, START, SUSPEND

DATE\$

Explanation Acquires the date as a "yyyy/mm/dd" format character string.

"yyyy" indicates the year, "mm" indicates the month, and "dd" indicates the day.

Date setting is performed from an operation terminal such as a pendant.

SAMPLE

A\$=DATE\$
PRINT DATE\$
HALT

Related commands

TIME\$

\_\_\_

C

D

E

F

G

H

J

K

L

D

#### **Format**

- 1. DECEL [<robot number>] <expression>
- 2. DECEL [<robot number>] (<axis number>) =<expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......1 to 100 (units: %)

Explanation Change the deceleration rate parameter of a robot axis specified by the <robot number> to the <expression> value. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

In format 1, the change occurs at all axes of a specified robot.

In format 2, the change occurs at the axis specified in <axis number>. .....



- If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and command execution is stopped.
- Command statement ACCEL can be used to change the acceleration parameter.

#### **Functions**

#### **Format**

DECEL [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number> ...... 1 to 6

Explanation Acquires the deceleration rate parameter value for the axis specified by the <axis number> among the robot axis specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

```
SAMPLE
A = 50
```

```
DECEL A
DECEL(3) = 100
'CYCLE WITH INCREASING DECELERATION
FOR A =10 TO 100 STEP 10
  DECEL A
  MOVE P , PO
  MOVE P , P1
NEXT A
A=DECEL(3) ..... The
                              deceleration rate
                        parameter for the axis 3
                        of robot 1 is assigned to
                        variable A.
HALT "END TEST "
```

## DEF FN

Defines functions which can be used by the user

#### **Format**

Values

<name> ......Function name. Max. of 16 chars., including "FN". <dummy argument> ......Numeric or character string variable.

**Explanation** Defines the functions which can be used by the user. Defined functions are called in the FN <name> (<variable>) format.

**MEMO** 

- The <dummy argument> names are the same as the variable names used in the <function definition expression>. The names of these variables are valid only when the <function definition expression> is evaluated. There may be other variables with the same name in the program.
- When calling a function that uses a <dummy argument>, specify the constant, variable, or expression type which is the same as the <dummy argument> type. The <dummy argument> can be omitted.
- If a variable used in the <function definition expression> is not included in the <dummy argument> list, the current value of that particular variable is used for the calculation.
- A space must be entered between "DEF" and "FN". If no space is entered, DEFFN will be handled as a variable.
- The DEF FN statement cannot be used in sub-procedures.
- Definition by the DEF FN statement must be declared before statements which use functions.

#### SAMPLE

Α

B

C

D

E

F

G

Ŀ

K

ı

M

DEGRAD (<expression>)

Values

<expression>.....Angle (units: degrees)

**Explanation** The <expression> value is converted to radians. To convert radians to degrees, use RADDEG.

SAMPLE

A=COS(DEGRAD(30)) ······ A 30° cosine value is assigned to variable A.

Related commands

ATN, COS, RADDEG, SIN, TAN

D

DELAY <expression>

Values <expression>......1 to 3600000 (units: ms)

Explanation A "program wait" status is established for the period of time specified by the <expression>. The minimum wait period is 1ms.

#### SAMPLE

DELAY 3500 ..... 3,500ms (3.5 secs) wait DELAY A\*10

Acquires the input status from the parallel port

#### **Format**

```
1. [LET] <expression> = DIm([b, \cdots, b])
   [LET]
           <expression> = DI(mb, \cdot \cdot \cdot, mb)
```

Values

m ......Port No.: 0 to 7, 10 to 17, 20 to 27 b ......Bit definition: 0 to 7

**Explanation** Indicates the parallel input signal status.

If multiple bits are specified, they are expressed from the left in descending order (large to small).

Enter "0" if no input port exists.

If the [b,...,b] data is omitted, all 8 bits are processed.

154	M	MA	193	ш	15
	T.		7.7		-

D11111	
	ne input status from DI (27) o DI (20) is assigned to
va	riable A%.
A%=DI5(7,4,0) Th	ne DI (57), DI (54), DI (50)  Iput status is assigned to
	riable A% (when all the above
A%=DI(37,25,20) Th	
	uput status is assigned to ariable A% (when all the
ak	oove signals except DI (20)
ar	re "1" $(ON)$ , $A% = 6$ ).

Reference

For details, refer to Chapter 3 "9.3 Parallel input variable".

D

DIM

Ē

1

L

Format

DIM <array definition> [, <array definition>,…]

Array definition

Values

<constant> ......Array subscript: 0 to 32,767 (positive integer)

Explanation Directly declares the name and length (number of elements) of an array variable. A maximum of 3 dimensions may be used for the array subscripts. Multiple arrays can be declared in a single line by using comma (, , ) breakpoints to separate the arrays.

**MEMO** 

• Array subscripts can be "0 to a specified value", with their total number being the <constant> + 1.

.....

• A "9.31: Memory full" error may occur depending on the size of each dimension defined in an array.

```
DIM A%(10) Defines a integer array variable A% (0) to A% (10).

(Number of elements: 11).

DIM B(2,3,4) Defines a real array variable B (0, 0, 0) to B (2, 3, 4).

(Number of elements: 60).

DIM C%(2,2),D!(10) Defines an integer array C% (0,0) to C% (2,2) and a real array D! (0) to D! (10).
```

Acquires the distance between 2 specified points

#### **Format**

DIST (<point expression 1>,<point expression 2>)

Values

<point expression 1>.....Cartesian coordinate system point <point expression 2>.....Cartesian coordinate system point

Explanation Acquires the distance (X,Y,Z)between the 2 points specified by <point expression 1> and <point expression 2>. An error occurs if the 2 points specified by each <point expression> do not have a Cartesian coordinates.

#### SAMPLE

A=DIST(P0,P1) ..... The distance between P0 and P1 is assigned to variable A.

D

1. [LET] DOm  $([b, \cdot \cdot \cdot, b])$ = <expression> 2. [LET] DO  $(mb, \dots, mb)$ = <expression>

#### Values

m: Port No. ......2 to 7, 10 to 17, 20 to 27

b: Bit definition ...... 0 to 7

The output value is the lower left-side bit of the integer-converted <expression> value.

**Explanation** Directly outputs the specified value to the DO port.

If multiple bits are specified, they are expressed from the left in descending order (large to small).

No output will occur if a nonexistent DO port is specified.

If the [b,...,b] data is omitted, all 8 bits are processed.

Outputs are not possible to DO0() and DO1(). These ports are for referencing only.

#### SAMPLE

DO2() = &B10111000 ..... DO (27, 25, 24, 23) are turned ON, and DO (26, 22, 21, are turned OFF.

 $DO2(6,5,1) = \&B010 \cdots DO(25)$  are turned ON, and DO (26, 21) are turned OFF.

DO3() = 15 ····· DO (33, 32, 31, 30) are turned ON, and DO (37, 36, 35, 34) are turned OFF.

 $DO(37,35,27,20) = A \cdots$  The contents of the 4 lower bits acquired when variable A is converted to an integer are output to DO (37, 35, 27, 20) respectively.

Related commands

RESET, SET

D

Executes absolute movement of specified axes

#### **Format**

DRIVE [<robot number>] (<axis number>, <expression>) [,(<axis number>, <expression>)...] [, option]

Values

<robot number> ...... 1 to 4 <axis number>......1 to 6 <expression>......Motor position (mm, degrees, pulses) or point expression

Explanation Executes absolute movement command for specified axis of the robot specified by the <robot number>.

The <robot number> can be omitted. If it is omitted, robot 1 is specified.

This command is also used in the same way for the auxiliary axes.

- Movement type: PTP movement of specified axis.
- Point setting method: By direct numeric value input and point definition.
- Options: Speed setting, STOPON conditions setting, XY setting.movement direction setting. Multiple options can be specified.

#### Movement type

#### PTP (Point to Point) movement of specified axis:

PTP movement begins after positioning of all axes specified at <axis number> is complete (within the tolerance range), and the command terminates when the specified axes enter the OUT position range. When two or more axes are specified, they will reach their target positions simultaneously.

If the next command following the DRIVE command is an executable command such as a signal output command, that next command will start when the movement axis enters the OUT position range. In other words, that next command starts before the axis arrives within the target position tolerance range.

#### Example:


Signal output (DO, etc.)	Signal is output when axis enters within OUT position range.
DELAY	DELAY command is executed and standby starts, when axis enters the OUT position range.
HALT	Program stops and is reset when axis enters the OUT position range. Therefore, axis movement also stops.
HALTALL	All programs in execution stop when axis enters the OUT position range, task 1 is reset, and other tasks terminate. Therefore, the movement also stops.
HOLD	Program temporarily stops when axis enters the OUT position range. Therefore, axis movement also stops.
HOLDALL	All programs in execution temporarily stop when axis enters the OUT position range. Therefore, the movement also stops.
WAIT	WAIT command is executed when axis enters the OUT position range.


28

**DRIVE** 

The WAIT ARM statement is used to execute the next command after the axis enters the tolerance range.

#### **DRIVE** command





33819-R7-00

#### SAMPLE

#### Point data setting types

#### Direct numeric value input

The motor position is specified directly in <expression>.

If the motor position's numeric value is an integer, this is interpreted as a "pulse" units. If the motor position's numeric value is a real number, this is interpreted as a "mm/degrees" units, and each axis will move from the 0-pulse position to a pulse-converted position.

However, when using the optional XY setting, movement occurs from the coordinate origin position.

## SAMPLE

D


# Point definition Point data is specified.

Point data is specified in <expressions>. The axis data specified by the <axis number> is used. If the point expression is in "mm/degrees" units, movement for each axis occurs from the 0-pulse position to the pulse-converted position.

However, when using the optional XY setting, movement occurs from the coordinate origin position.

# NOTE

 If point data is specified with both integers and real numbers in the same statement, all values are handled in "mm/degrees" units.



pulse position. (When axis 4 is a rotating axis.)

Option types

#### Speed setting

#### Format

- 1. SPEED =<expression>
- 2. S =<expression>

Values <expression>......1 to 100 (units: %)

program movement speed (%).

Explanation The program's movement speed is specified as an <expression>.

The actual speed is determined as shown below.

• Robot's max. speed (mm/sec, or deg/sec) × automatic movement speed (%) ×

This option is enabled only for the specified DRIVE statement.

#### SAMPLE

DRIVE[2](1,10000),  $S=10\cdots$  Axis 1 of robot 2 moves from its current position to the 10000 pulses position at 10% of the automatic movement speed.

#### Format

- 1. DSPEED =<expression>
- 2. DS =<expression>

Explanation The axis movement speed is specified in <expression>.

The actual speed is determined as shown below.

• Robot's max. speed (mm/sec, or deg/sec) × axis movement speed (%).

This option is enabled only for the specified DRIVE statement.

• Movement always occurs at the DSPEED <expression> value (%) without being affected by the automatic movement speed value (%).

#### SAMPLE

DRIVE[2](1,10000), DS=0.1  $\cdots$  Axis 1 of robot 2 moves from its current position to the 10000 pulses position at 0.1% of the maximum speed.



 This defines the maximum speed, and does not guarantee that all movement will occur at specified speed.



#### NOTE

SPEED option and DSPEED option cannot be used together

**DRIVE** 

#### \_\_

#### STOPON conditions setting

#### **Format**

STOPON < conditional expression>

#### **Explanation**

Stops movement when the conditions specified by the conditional expression are met. Because this is a deceleration type stop, there will be some movement (during deceleration) after the conditions are met.

If the conditions are already met before movement begins, no movement occurs, and the command is terminated.

This option is enabled only by program execution.

#### SAMPLE

DRIVE(1,10000),STOPON DI(20)=1



• When the conditional expression used to designate the STOPON condition is a numeric expression, expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

#### XY setting

#### **Format**

XY

#### Explanation

Moves multiple specified axes to a position specified by Cartesian coordinates.

All the specified axes arrive at the target position at the same time.

If all axes which can be moved by MOVE statement have been specified, operation is identical to that which occurs when using MOVE statement.

The following restrictions apply to this command:

- 1. Axes specified by <axis number> must include the axis 1 and 2.
- 2. This command can be specified at SCARA robots and XY robots.
- 3. Point settings must be in "mm" or "deg" units (real number setting).

#### SAMPLE

DRIVE(1,P100),(2,P100),(4,P100),XY

#### Movement direction setting

**Format** 

PLS MNS

**Explanation** 

<With a "movement direction setting">

- Movement occurs in the specified direction. A PLS setting always results in plus-direction movement, and a MNS setting always results in minus-direction movement.
- If the target position and the current position are the same, a 1-cycle movement amount occurs in the specified direction, then operation stops.

< Without a "movement direction setting">

- Movement occurs in the direction in which the movement distance is shortest.
- If the target position and the current position are the same, no movement occurs.

#### • Cautions

- When using this option, the maximum movement distance per operation is the distance equivalent to 1 cycle (360°). If movement which exceeds the 1-cycle distance is desired, the movement must be divided into 2 or more operations.
- 2. When using this option, the DRIVE statement's soft limit values are as shown below.

Plus-direction soft limit: 67,000,000 [pulse] Minus-direction soft limit: -67,000,000 [pulse]

#### • Restrictions

- 1. Only the axis of a single-axis rotary type robot can be specified.
- Simultaneous movement of multiple axes is not possible when a movement direction has been specified. If such movement is attempted, the "5.37: Specification mismatch" error will occur (see below).

Example: DRIVE (3,P1), (4,P1), PLS

- 3. The PLS and MNS options cannot both be specified simultaneously.
- 4. Attempting to use this option for a "limitless motion INVALID" axis will result in the "2.29: Cannot move without the limit" error.
- 5. If a stop is executed by pressing the [STOP] key, etc., during movement which uses this option (including during a deceleration), the movement distance when restarted will be equivalent to a 1-cycle distance (360°).

A

В

C

D

E

F

П

J

M

**DRIVE** 

```
SAMPLE
```

DRIVE (4,270.00), PLS

......When the robot current position is 260°: Moves 10° in the plus direction from the current position.

> When the robot current position is 280°: Moves 350° in the plus direction from the current position.

DRIVE (4,270.00), MNS

......When the robot current position is 260°: Moves 350° in the minus direction from the current position.

> When the robot current position is 280°: Moves 10° in the minus direction from the current position.

DRIVE (4,270.00)

......When the robot current position is 260°: Moves 10° in the plus direction from the current position.

> When the robot current position is 280°: Moves 10° in the minus direction from the current position.

DRIVE[2] (3,270.00), PLS

......When the robot current position is 260°: Moves 10° in the plus direction from the current position.

> When the robot current position is 280°: Moves 350° in the plus direction from the current position.

DRIVE[2] (3,270.00), MNS

......When the robot current position is 260°: Moves 350° in the minus direction from the current position.

When the robot current position is 280°: Moves 10° in the minus direction from the current position.

DRIVE[2] (3,270.00)

......When the robot current position is 260°: Moves 10° in the plus direction from the current position.

> When the robot current position is 280°: Moves 10° in the minus direction from the current position.

Moves the specified robot axes in a relative manner

#### **Format**

DRIVEI(<axis number>, <expression>)[,(<axis number>, <expression>)...][,option]

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......Motor position (mm, deg, pulses) or point expression.

Explanation Directly executes relative movement of each axis of a group, including the auxiliary axes.

• Movement type: PTP movement of a specified axis

• Point data setting: Direct coordinate data input, point definition

Speed setting, STOPON conditions setting multiple options specifiable • Options : 



· When DRIVEI motion to the original target position is interrupted and then restarted, the target position for the resumed movement can be selected as the "MOVEI/DRIVEI start position" in the controller's "other parameters". For details, refer to the controller manual.

1) KEEP (default setting) Continues the previous (before interruption) movement. The original

target position remains unchanged.

2) RESET Relative movement begins anew from the current position. The new

target position is different from the original one (before interruption).

#### Movement type

#### PTP (point-to-point) of specified axis

PTP movement begins after positioning of all axes specified at <axis number> is complete (within the tolerance range), and the command terminates when the specified axes enter the OUT position range. When two or more axes are specified, they will reach their target positions simultaneously.

If the next command following the DRIVEI command is an executable command such as a signal output command, that next command will start when the movement axis enters the OUT position range. In other words, that next command starts before the axis arrives within the target position tolerance range.

#### Example:

Signal output (DO, etc.)	Signal is output when axis enters within OUT position range.
DELAY	DELAY command is executed and standby starts, when axis enters the OUT position range.
HALT	Program stops and is reset when axis enters the OUT position range. Therefore, axis movement also stops.
HALTALL	All programs in execution stop when axis enters the OUT position range, task 1 is reset, and other tasks terminate. Therefore, the movement also stops.
HOLD	Program temporarily stops when axis enters the OUT position range. Therefore, axis movement also stops.
HOLDALL	All programs in execution temporarily stop when axis enters the OUT position range. Therefore, the movement also stops.
WAIT	WAIT command is executed when axis enters the OUT position range.

D


29


**DRIVEI** 

The WAIT ARM statement are used to execute the next command after the axis enters the tolerance range.

#### **DRIVEI** command

WAIT ARM statement





33820-R7-00

#### Limitless motion related cautions

• When the "limitless motion" parameter is enabled, the DRIVEI statement soft limit check values are as follows:

Plus-direction soft limit: 67,000,000 [pulse]
Minus-direction soft limit: -67,000,000 [pulse]

•When using the DRIVEI statement, the above values represent the maximum movement distance per operation.

# DRIVEI(1,P0) ...... The axis 1 moves from its current position to the position specified by P0.

В

C

ם

Ε

F

G

Н

K

ı

#### Point data setting types

#### Direct numeric value input

The motor position is specified directly in <expression>.

If the motor position's numeric value is a real number, this is interpreted as a "mm / deg" units, and each axis will move from the 0-pulse position to a pulse-converted position.

SAMPLE	
DRIVEI(1,10000)	The axis 1 moves from its
	current position to the "+10000 pulses" position.
DRIVEI(4,90.00)	The axis 4 moves from its current position to the +90° position (when axis 4 is a rotating axis).

# NOTE

 If point data is specified with both integers and real numbers in the same statement, all values are handled in "mm/degrees" units.

#### Point definition

Point data is specified in <expression>. The axis data specified by the <axis number> is used. The motor position is determined in accordance with the point data defined by the point expression. If the point expression is in "mm/degrees" units, movement for each axis occurs from the 0-pulse position to the pulse-converted position.

SAMPLE
DRIVEI(1,P1) The axis 1 moves from its
current position the distance specified by P1.
DRIVEI(4, P90) The axis 4 moves from its
current position the number of
degrees specified by P90 (when
axis 4 is a rotating axis).

A

В

D

J

A A

DRIVE

#### **Option types**

#### Speed setting

#### Format

- 1. SPEED=<expression>
- S=<expression>

Values

<expression>......1 to 100 (units: %)

#### **Explanation**

The program's movement speed is specified by the <expression>.

The actual speed is as follows:

• Robot's max. speed (mm/sec, or deg/sec) × automatic movement speed (%) × program movement speed (%).

This option is enabled only for the specified DRIVEI statement.

#### SAMPLE

DRIVEI(1,10000), S=10 ····· The axis 1 moves from its current position to the +10000 pulses position at 10% of the automatic movement speed.

#### **Format**

- 1. DSPEED=<expression>
- 2. DS=<expression>

Values

<expression>......0.01 to 100.00 (units: %)

#### **Explanation**

The axis movement speed is specified as an <expression>.

The actual speed is determined as shown below.

• Robot's max. speed (mm/sec, or deg/sec) × axis movement speed (%).

This option is enabled only for the specified DRIVEI statement.

• Movement always occurs at the DSPEED <expression> value (%) without being affected by the automatic movement speed value (%).

#### SAMPLE

DRIVEI(1,10000), DS=0.1  $\cdot\cdot$  The axis 1 moves from its current position to the +10000 pulses position at 0.1% of the automatic movement speed.

#### NOTE

 This defines the maximum speed, and does not guarantee that all movement will occur at specified speed.

# NOTE

SPEED option and DSPEED

option cannot be used together.

#### STOPON conditions setting

#### **Format**

STOPON <conditional expression>

#### **Explanation**

Stops movement when the conditions specified by the conditional expression are met. Because this is a deceleration type stop, there will be some movement (during deceleration) after the conditions are satisfied.

If the conditions are already satisfied before movement begins, no movement occurs, and the command is terminated.

This option is enabled only by program execution.



• When the conditional expression used to designate the STOPON condition is a numeric expression, expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

.....

#### SAMPLE

DRIVEI(1,10000), STOPON DI(20)=1

A

В

C

D

E

F

G

Ш

L

M

## **END SELECT**

Ends the SELECT CASE statement

```
Format
SELECT [CASE] <expression>
   CASE <expression's list 1>
      [command block 1]
   CASE <expression's list 2>
      [command block 2]
   [CASE ELSE
      [command block n]
END SELECT
```

**Explanation** Directly ends the SELECT CASE command block. For details, see section "92 SELECT CASE to END SELECT".

```
SAMPLE
WHILE -1
SELECT CASE DI3()
   CASE 1,2,3
      CALL *EXEC(1,10)
   CASE 4,5,6,7,8,9,10
      CALL *EXEC(11,20)
   CASE ELSE
      CALL *EXEC(21,30)
END SELECT
WEND
HALT
```

Related commands

SELECT CASE

Ends the sub-procedure definition

```
Format
```

Explanation Ends the sub-procedure definition which begins at the SUB statement. For details, see section "105 SUB to END SUB".

```
I=1
CALL *TEST
PRINT I
HALT
'SUB ROUTINE: TEST
SUB *TEST
I=50
END SUB
```

Related commands

CALL, EXIT SUB, SUB to END SUB

ERR(<task number>) ERL(<task number>)

Values

<task number>......1 to 4

Explanation Variables ERR and ERL are used in error processing routines specified by the ON ERROR GOTO statement.

> ERR of the task specified by the <task number> gives the error code of the error that has occurred and ERL gives the line number in which the error occurred.

#### SAMPLE 1

IF ERR (1) <> &H604 THEN HALT IF ERL (1) =20 THEN RESUME NEXT

Related commands

ON ERROR GOTO, RESUME

EXIT FOR

Explanation Directly terminates the FOR to NEXT statement loop, then jumps to the command which follows the NEXT statement.

This statement is valid only between the FOR to NEXT statements.



• The FOR to NEXT statement loop will end when the FOR statement condition is satisfied or when the EXIT FOR statement is executed. A "5.12: Stack overflow" error, etc., will occur if another statement such as GOTO is used to jump out of the loop.

\_\_\_\_\_

#### SAMPLE

```
*ST:
WAIT DI(20)=1
FOR A%=101 TO 109
  MOVE P, P100, Z=0
   DO(20) = 1
  MOVE P,P[A%],Z=0
  DO(20) = 0
   IF DI(20)=0 THEN EXIT FOR
NEXT A%
GOTO
      *ST
HALT
```

Related commands

FOR, NEXT

EXIT SUB

Explanation The EXIT SUB statement terminates the sub-procedure defined by the SUB to END SUB statements, then jumps to the next command in the CALL statement that called up the sub-procedure.

> This statement is valid only within the sub-procedure defined by the SUB to END SUB statements.



• To end the sub-procedure defined by the SUB to END SUB statements, use the END SUB statement or EXIT SUB statement. A "5.12: Stack overflow" error, etc., will occur if another statement such as GOTO is used to jump out of the loop.

#### SAMPLE

```
' MAIN ROUTINE
     *SORT2(REF X%, REF Y%)
HALT
 SUB ROUTINE: SORT
SUB *SORT2(X%, Y%)
   IF X%>=Y% THEN EXIT SUB
  TMP%=Y%
  Y%=X%
  X%=TMP%
END SUB
```

Related commands

CALL, SUB to END SUB, END SUB

Terminates its own task which is in progress

```
Format
```

EXIT TASK

Explanation Terminates its own task which is currently being executed.

```
SAMPLE
' TASK1 ROUTINE
*ST:
   MO(20) = 0
   START <SUB_PGM>,T2
   MOVE P, P0, P1
   WAIT MO(20)=1
   GOTO *ST
HALT
Program name:SUB_PGM
*SUBPGM:
' TASK2 ROUTINE
*SUBTASK2:
   P100=JTOXY(WHERE)
   IF LOCZ(P100)>=100.0 THEN
      MO(20) = 1
      EXIT TASK
   ENDIF
   DELAY 100
GOTO *SUBPGM
EXIT TASK
```

Related commands

CUT, RESTART, START, SUSPEND, CHGPRI

A

В

C

D

E

F

. .

J

K

L

M

#### FOR to NEXT

Performs loop processing until the variable-specified value is exceeded

#### **Format**

```
FOR <control variable> = <start value> TO <end value> [STEP] <step>]
   <command block>
NEXT [<control variable>]
```

Explanation These direct statements repeatedly execute commands between the FOR to NEXT statements for the <start value> to <end value> number of times, while changing the <control variable> value in steps specified by <STEP>. If <STEP> is omitted, its value becomes "1".

The <STEP> value may be either positive or negative.

The <control variable> must be a numeric <simple variable> or <array variable>.

The FOR and NEXT statements are always used as a set.

#### SAMPLE

```
'CYCLE WITH CYCLE NUMBER OUTPUT TO DISPLAY
FOR A=1 TO 10
  MOVE P, P0
  MOVE P, P1
  MOVE P, P2
   PRINT"CYCLE NUMBER="; A
NEXT A
HALT
```

Related commands

**EXIT FOR** 

**Format** GOSUB < label> \* GOSUB can also be expressed as "GO SUB". <label>: : RETURN

Explanation Jumps to the <label> sub-routine specified by the GOSUB statement.

A RETURN statement within the sub-routine causes a jump to the next line of the GOSUB statement.



- The GOSUB statement can be used up to 120 times in succession. Note that this number of times is reduced if commands containing a stack such as an FOR statement or CALL statement
- When a jump to a subroutine was made with the GOSUB statement, always use the RETURN statement to end the subroutine. If another statement such as GOTO is used to jump out of the subroutine, an error such as "5.12: Stack overflow" may occur.

### SAMPLE \*ST: MOVE P, P0 GOSUB \*CLOSEHAND MOVE P, P1 GOSUB \*OPENHAND GOTO \*ST HALT ' SUB ROUTINE \*CLOSEHAND: DO(20) = 1RETURN \*OPENHAND: DO(20) = 0RETURN

Related commands

**RETURN** 

Ε

в

K

L

```
GOTO <label> * GOTO can also be expressed as "GO TO".
```

Explanation Executes an unconditional jump to the line specified by <label>.

To select a conditional jump destination, use the ON to GOTO, or IF statements.

```
MAIN ROUTINE

*ST:
   MOVE P,P0,P1
   IF DI(20) = 1 THEN
      GOTO *FIN
   ENDIF
GOTO *ST
   *FIN:
HALT
```

Stops the program and performs a reset

**Format** 

HALT [ <expression> <character string>

Explanation Directly stops the program and resets it. If restarted after a HALT, the program runs from its beginning.

> If an <expression> or <character string> is written in the statement, the contents of the <expression> or <character string> are displayed on the programming box screen.

· HALT is effective only in the task executed. The programs executed in other tasks continue execution.

```
SAMPLE
```

```
' MAIN ROUTINE
*ST:
  MOVE P, P0, P1
  IF DI(20) = 1 THEN
    GOTO *FIN
  ENDIF
GOTO *ST
*FIN:
HALT "PROGRAM FIN"
```


In PTP movement specified by movement commands such as MOVE and DRIVE, the next line's command is executed when the axis enters the OUT position range.

Therefore, if a HALT command exists immediately after a PTP movement command, that HALT command is executed before the axis arrives in the target position tolerance range.

Likewise, in interpolation movement during MOVE command, the next command is executed immediately after movement starts. Therefore, if a HALT command exists immediately after the interpolation movement command during MOVE, that HALT command is executed immediately after movement starts.

In either of the above cases, use the WAIT ARM command if desiring to execute the HALT command after the axis arrives within the target position tolerance range.

#### **HALT** command



33821-R7-00

D

## HALTALL

Stops all programs and performs reset.

#### **Format** HALT [ <expression> <character string>

Explanation Directly stops all programs and reset them. If restarted after a HALTALL, the program runs from its beginning of the main program or the program that is executed lastly in task 1. If an <expression> or <character string> is written in the statement, the contents of the <expression> or <character string> are displayed on the programming box screen.


```
SAMPLE
 ' MAIN ROUTINE
 *ST:
   MOVE P, P0, P1
   IF DI(20) = 1 THEN
      GOTO *FIN
   ENDIF
 GOTO *ST
 *FIN:
 HALT "PROGRAM FIN"
```

In PTP movement specified by movement commands such as MOVE and DRIVE, the next line's command is executed when the axis enters the OUT position range.

Therefore, if a HALTALL command exists immediately after a PTP movement command, that HALTALL command is executed before the axis arrives in the target position tolerance range.

Likewise, if the CONT option is specified in the interpolation movement during MOVE command, the next command is executed immediately after movement starts. Therefore, if a HALTALL command exists immediately after the interpolation movement command with the CONT option specified during MOVE, that HALTALL command is executed immediately after movement starts. In either of the above cases, use the WAIT ARM command if desiring to execute the HALTALL command after the axis arrives within the target position tolerance range.

#### **HALTALL** command



33701-R9-00

Definition statement:

HAND[<robot number>] Hn = <1st parameter> <2nd parameter> <3rd parameter> [R] Selection statement:

CHANGE [<robot number>] Hn

Values

<robot number>......1 to 4 n: hand No......0 to 31

Explanation The HAND statement only defines the hand. To actually change hands, the CHANGE statement must be used.

For CHANGE statement details, see section "12 CHANGE".

**MEMO** 

 If a power OFF occurs during execution of the hand definition statement, the "9.7 Hand checksum error" may occur.

#### For SCARA Robots 41.1

# ■ 1. When the <4th parameter> "R" is not specified

Hands installed on the second arm tip are selected (see below).

<1st parameter> ...... Number of offset pulses between the standard second arm position and the virtual second arm position of hand "n". "+" indicates the


counterclockwise direction [pulse].

<2nd parameter> ...... Difference between the hand "n" virtual second arm length and the

standard second arm length. [mm]

<3rd parameter> ...... Z-axis offset value for hand "n". [mm]

#### When the <4th parameter> "R" is not specified:





33803-R9-00

41

SAMPLE										
HAND H1=	0	150.0	0.0	)						
HAND H2=	-5000	20.00	0.0	)						
P1=	150.00	300.00	0.00	)	0.0	0	0.0	0	0.	00
CHANGE H2										
MOVE P, P1		• • • • • • • • • • • • • • • • • • • •	$\cdots$ Tip	of	hand	2	moves	to	P1.	0
CHANGE H1	=									
MOVE P, P1		• • • • • • • • • • • • • • • • • • • •	$\cdot \cdot$ Tip	of	hand	1	moves	to	P1.	2
HALT										

## SAMPLE:HAND





# ■ 2. When the <4th parameter> "R" is specified


If the R-axis uses a servo motor, the hands that are offset from the R-axis rotating center are selected (see below).

[degree]

<2nd parameter> ...... Length of hand "n". [mm] (>0)

<3rd parameter> ...... Z-axis offset amount for hand "n". [mm]


# When the <4th parameter> "R" is specified




33804-R9-00

SAMPLE										
HAND H1=	0.00	150.0	0.	0		R				
HAND H2=	-90.00	100.00	0.	0		R				
P1=	150.00	300.00	0.0	0	0.0	0 0	0.0	0	0.	00
CHANGE H1	-									
MOVE P, P1		• • • • • • • • • • • • • • • • • • • •	·Tip	of	hand	1	moves	to	P1.	0
CHANGE H2	2									
MOVE P, P1			·Tip	of	hand	2	moves	to	P1.	2
HALT										

# SAMPLE:HAND





D

E

F

G

\_

K

L


# 41.2 For Cartesian Robots

# 1. When the <4th parameter> "R" is not specified

Hands installed on the second arm tip are selected (see below).

<1st parameter> ...... Hand "n" X-axis offset amount [mm] <2nd parameter> ..... Hand "n" Y-axis offset amount [mm] <3rd parameter> ..... Hand "n" Z-axis offset amount [mm]


# When the <4th parameter> "R" is not specified




33805-R9-00

SAMPLE HAND H1= 0.00 0.00 0.00 HAND H2= 100.0 -100.0 -100.0 P1= 200.00 250.00 0.00 0.00 0.00 0.00 CHANGE H2 MOVE P,P1 ..... Tip of hand 2 moves to P1. 1 CHANGE H1  $\cdots$  Tip of hand 1 moves to P1. 2 MOVE P, P1 · HALT

# SAMPLE:HAND





A

B

C

D

E

F

J

М

# 2. When the <4th parameter> "R" is specified

If the R-axis uses a servo motor, the hands that are offset from the R-axis rotating center are selected (see below).


<1st parameter> ....... When the current position of R-axis is 0.00, this parameter shows the angle of hand "n" from the X-axis plus direction in a Cartesian coordinate system. ("+"indicates the counterclockwise direction.)

[degree]

<2nd parameter> ...... Length of hand "n". [mm] (>0)

<3rd parameter> ...... Z-axis offset amount for hand "n". [mm]


# When the <4th parameter> "R" is specified




33806-R9-00

SAMPLE										
HAND H1=	0.00	100.00	0.00			R				
HAND H2=	90.00	150.00	0.00			R				
P1=	200.00	250.00	0.00		0.0	0	0.0	0	0.	00
CHANGE H2	2									
MOVE P, P1	L	• • • • • • • • • • • • • • • • • • • •	·Tip o	f	hand	2	moves	to	P1.	0
CHANGE H1	L									
MOVE P, P1	L	• • • • • • • • • • • • • • • • • • • •	·Tip o	f	hand	1	moves	to	P1.	2
HALT										

# SAMPLE:HAND





33808-R7-00

HOLD

# **Format** HOLD [ <expression> <character string>

Explanation Temporarily stops the program. When restarted, processing resumes from the next line after the HOLD statement. If an <expression> or <character string> is written in the statement, the contents of the <expression> or <character string> display on the programming box screen.



· HOLD is effective only in the task executed. The programs executed in other tasks continue

```
SAMPLE
 MAIN ROUTINE
*ST:
   MOVE P, P0, P1
   IF DI(20)=1 THEN
      HOLD "PROGRAM STOP"
   ENDIF
GOTO *ST
HALT
```


In PTP movement specified by movement commands such as MOVE and DRIVE, the next line's command is executed when the axis enters the effective OUT position range.

Therefore, if a HOLD command exists immediately after a PTP movement command, that HOLD command is executed before the axis arrives in the target position tolerance range.

Likewise, in interpolation movement during MOVE command, the next command is executed immediately after movement starts. Therefore, if a HOLD command exists immediately after the interpolation movement command during MOVE, that HOLD command is executed immediately after movement starts.

In either of the above cases, use the WAIT ARM command if desiring to execute the HOLD command after the axis arrives within the target position tolerance range.

#### **HOLD** command



33822-R7-00

Temporality stops all programs.

# **Format** HOLD[ <expression> <character string>

Explanation Temporality stops all programs. When restarted, the program that has executed HOLDALL is executed from the next line after the statement, and other programs are resumed from the line that has interrupted execution. If an <expression> or <character sting> is written in the statement, the contents of <expression> or <character string> displays on the programming box screen.


```
SAMPLE
' MAIN ROUTINE
*ST:
   MOVE P, P0, P1
   IF DI(20)=1 THEN
      HOLD "PROGRAM STOP"
   ENDIF
GOTO *ST
HALT
```

In PTP movement specified by movement commands such as MOVE and DRIVE, the next line's command is executed when the axis enters the effective OUT position range.

Therefore, if a HOLDALL command exists immediately after a PTP movement command, that HOLDALL command is executed before the axis arrives in the target position tolerance range.

Likewise, if the CONT option is specified in the interpolation movement during MOVE command, the next command is executed immediately after movement starts. Therefore, if a HOLDALL command exists immediately after the interpolation movement command with the CONT option specified during MOVE, that HOLDALL command is executed immediately after movement starts. In either of the above cases, use the WAIT ARM command if desiring to execute the HOLDALL command after the axis arrives within the target position tolerance range.

# **HOLDALL** command



33702-R9-00

Н

IF

 When the conditional expression used to designate the IF statement condition is a numeric expression, an expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

#### Simple IF statement 44.1

# **Format**

```
IF <conditional expression> THEN | < label 1> | [ELSE | < label 2>
                                        <command statement 1>
                                                               <command statement 2>
```

Explanation If the condition specified by the <conditional expression> is met, processing jumps either to the <label 1> which follows THEN, or to the next line after <command statement 1> is executed.

> If the condition specified by the <conditional expression> is not met, the following processing occurs:

- 1. Processing either jumps to the <label 2> specified after the ELSE statement, or to the next line after <command statement 2> is executed.
- 2. If nothing is specified after the ELSE statement, no action is taken, and processing simply jumps to the next line.

```
SAMPLE
```

```
' MAIN ROUTINE
*ST:
  MOVE P, P0, P1
  IF DI(20)=1 THEN *L1 ···· If DI (20) is "1", a jump to
                          *L1 occurs.
  DO(20) = 1
  DELAY 100
*L1:
   IF DI(21)=1 THEN *ST ELSE *FIN
         ...... If DI (21) is "1", a jump to
                          *ST occurs. If other than "1",
                          a jump to *FIN occurs.
*FIN:
HALT
```

#### 44.2 **Block IF statement**

```
Format
IF <conditional expression 1> THEN
   <command block 1>
[ELSEIF <conditional expression 2> THEN
   <command block 2>]
[ELSE
   <command block n>]
ENDIF
```

Explanation If the condition specified by <conditional expression 1> is met, this statement executes the instructions specified in <command block 1>, then jumps to the next line after ENDIF.

> When an ELSEIF statement is present and the condition specified by <conditional expression 2> is met, the instructions specified in <command block 2> are executed. If all the conditions specified by the conditional expression are not met, <command block n> is executed.

```
SAMPLE
```

```
' MAIN ROUTINE
*ST:
   MOVE P, P0, P1
   IF DI(21,20)=1 THEN
      DO(20) = 1
      DELAY 100
      WAIT DI(20) = 0
   ELSEIF DI (21,20) = 2 THEN
      DELAY 100
   ELSE
      GOTO *FIN
   ENDIF
GOTO *ST
*FIN:
HALT
```

INPUT

A

В

C

Е

Г

ı

J

K

Format		
INPUT [ <prompt statement=""></prompt>	;   ]	<pre><variable></variable></pre>

**Explanation** 

Assigns a value to the variable specified from the programming box.

The input definitions are as follows:

- 1. When two or more variables are specified by separating them with a comma ( , ), the specified input data items must also be separated with a comma ( , ).
- 2. At the <prompt statement>, enter a character string enclosed in quotation marks (" ") that will appear as a message requiring data input. When a semicolon (;) is entered following the prompt statement, a question mark (?) and a space will appear at the end of the message. When a comma (,) is entered, nothing will be displayed following the message.
- 3. When the cprompt statement> is omitted, only a question mark (?) and a space
  will be displayed.
- 4. The input data type must match the type of the corresponding variables. When data is input to a point variable or shift variable, insufficient elements are set to "0".
- 5. If only the ENTER key is pressed without making any entry, the program interprets this as a "0" or "null string" input. However, if specifying two or more variables, a comma (, ) must be used to separate them.
- 6. If the specified variable is a character type and a significant space is to be entered before and after a comma (, ), double quotation mark ( " ) or character string, the character string must be enclosed in double quotation marks ( " ). Note that in this case, you must enter two double quotation marks in succession so that they will be identified as a double quotation mark input.
- 7. Pressing the ESC key skips this command.



- If the variable and the value to be assigned are different types, the specified message displays, and a "waiting for input" status is established.
- When assigning alphanumeric characters to a character variable, it is not necessary to enclose the character string in double quotation marks ( " ).

```
INPUT A
INPUT "INPUT POINT NUMBER"; A1
INPUT "INPUT STRING", B$(0), B$(1)
INPUT P100
HALT
```

Truncates decimal fractions

# Format

INT (<expression>)

**Explanation** This function acquires an integer value with decimal fractions truncated. The maximum integer value which does not exceed the <expression> value is acquired.

# SAMPLE

A=INT(A(0))

B=INT(-1. 233) ....."-2" is assigned to B.

A

D

C

D

E

F

ш

L

M

# **Format**

**JTOXY** 

JTOXY [<robot number>] (<point expression>)

Values

<robot number>......1 to 4

Explanation Converts the joint coordinate data (unit: pulse) specified by the <point expression> into Cartesian coordinate data (unit: mm, degree) of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified. On YK500TW model robot, the first arm and the second arm rotation information are also set.

# SAMPLE

P10=JTOXY(WHERE) ..... Current position data converted to Cartesian coordinate data.

Related commands

XYTOJ

(<character string expression> , <expression>)

Values

<expression>......0 to 25

Explanation This function extracts a character string with the digits specified by the <expression> from the left end of the character string specified by <character string expression>. The <expression> value must be between 0 and 25, otherwise an error will occur. If the <expression> value is 0, then LEFT\$ will be a null string (empty character string).

> If the <expression> value has more characters than the <character string expression>, LEFT\$ will become the same as the <character string expression>.

SAMPLE

B\$=LEFT\$(A\$,4) .....4 characters from the left end of A\$ are assigned to B\$.

Related commands

MID\$, RIGHT\$

# **Format**

**LEFTY** 

LEFTY [<robot number>]

Values

<robot number>......1 to 4

**Explanation** 

This statement specifies the robot specified by the <robot number> so that it moves as a left-handed system to a point specified in the Cartesian coordinates. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

This statement only selects the hand system, and does not move the robot. If executed while the robot arm is moving, execution waits until movement is complete (positioned within tolerance range).

This command is only valid for SCARA robots.

# SAMPLE

RIGHTY

MOVE P, P1


LEFTY

MOVE P, P1

RIGHTY

HALT

# SAMPLE:LEFTY/RIGHTY



33809-R7-00

Related commands

**RIGHTY** 

A

J

ע

E

F

G

Н

K

L

Acquires a character string length

Format

LEN(<character string expression>)

**Explanation** Returns the length (number of bytes) of the <character string expression>.

SAMPLE

B=LEN(A\$)

Δ

Ď

D

E

F

П

J

۱

M

LET

**Format** LET

<arithmetic assignment statement> <character string assignment statement> <point assignment statement> <shift assignment statement>

Explanation Directly executes the specified assignment statement. The right-side value is assigned to the left side. An assignment statement can also be directly written to the program without using a LET statement.



• If the controller power is turned off during execution of a <point assignment statement> or <shift assignment statement>, a memory-related error such as the "9.2: Point check-sum error" or the "9.6: Shift check-sum error" may occur.

# 1. Arithmetic assignment statement

# **Format**

[LET] <arithmetic variable> <parallel output variable> <internal output variable> <arm lock output variable> <timer output variable> <serial output variable>

= <expression>

Values <expression>......Variable, function, numeric value

The <expression> value is assigned to the left-side variable. (Explanation)

#### SAMPLE

A! = B! + 1B%(1,2,3) = INT(10.88)DO2() = &B00101101MO(21,20)=2LO(00) = 1TO(01) = 0SO12() = 255

# 2. Character string assignment statement

### **Format**

[LET] <character string variable> = <character string expression>

### **Explanation**

The <character string expression> value is assigned to the character string variable. Only the plus (+) arithmetic operator can be used in the <character string expression>. Other arithmetic operators and parentheses cannot be used.

## SAMPLE

A\$ ="YAMAHA" B\$ ="ROBOT" D\$ = A\$ + "-" + B\$

Execution result: YAMAHA-ROBOT



• The "+" arithmetic operator is used to link character strings.

# 3. Point assignment statement

### **Format**

[LET] <point variable> = <point expression>

## **Explanation**

Assigns <point expression> values to point variables.

Only 4 arithmetic operators (+, -\*, /) can be used in the <point expression>. Multiplication and division are performed only for constant or variable arithmetic operations.

- Addition/subtraction ....... Addition/subtraction is performed for each element of each axis.
- Multiplication ...... Multiplication by a constant or variable is performed for each element of each axis.
- Division ...... Division by a constant or variable is performed for each element of each axis.

Multiplication results vary according to the point data type.

- For pulse units ...... Assigned after being converted to an integer.
- For "mm" units ...... Assigned after being converted to a real number down to the 2nd decimal position.

SAMPLE
P1 =P10 ····· Point 10 is assigned to P1. P20=P20+P5 ···· Each element of point 20 and point 5 is summed and assigned to P20.
P30=P30-P3 ······ Each element of point 3 is subtracted from point 30 and assigned to P30.
P80=P70*4····· Each element of point 70 is multiplied by 4 and assigned to P80.
P60=P5/3·····Each element of point 5 is divided by 3 and assigned to P60.



- Multiplication & division examples are shown below.
  - Permissible examples ...... P15 \* 5, P[E]/A, etc.
  - Prohibited examples ....... P10 \* P11, 3/P10, etc.

# 4. Shift assignment statement

# **Format**

<shift variable> = <shift expression>

# **Explanation**

Assigns <shift expression> values to shift variables.

Only shift elements can be used in <shift expressions>, and only addition and subtraction arithmetic operators are permitted. Parentheses cannot be used.

• Addition/subtraction .......Addition/subtraction is performed for each element of each axis.

# SAMPLE

is assigned "shift 1". S2=S1+S0····· Each element of "shift 1" and "shift 0" is summed and assigned to "shift 2".



- Examples of <shift expression> addition/subtraction:
  - Permissible examples ...... S1 + S2
  - Prohibited examples ...... S1 + 3

### **Format**

1. LOm ( $[b, \dots, b]$ ) = <expression> 2. LO  $(mb, \dots, mb) = \langle expression \rangle$ 

Values

m: port number ......0, 1 b: Bit definition ......0 to 7 <expression>......Converted to an integer. The lower bits corresponding

Explanation This statement outputs the specified value to the LO port to either prohibit or allow axis movement.

to the bits specified on the left side are valid.

LO(00) to LO(17) respectively correspond to axes 1 to 16. An arm lock ON status occurs at axes where bits are set, and axis movement is prohibited. Multiple bits must be specified in descending order from left to right (large  $\rightarrow$  small).

**MEMO** 

This statement is valid at axes where movement is started.

### SAMPLE

LOO()=&B00001010.....Prohibits movement at axes 2 and 4.  $LOO(2,1) = \&B10 \cdots$  Prohibits movement at axis 3.

Related commands

RESET, SET

Specifies/acquires point data for a specified axis or shift data for a specified element.

### **Format**

1. LOCx	( <point< th=""><th>expression&gt;)</th><th>=</th><th><expression></expression></th></point<>	expression>)	=	<expression></expression>
2. LOCx	( <shift< td=""><td>expression&gt;)</td><td>=</td><td><expression></expression></td></shift<>	expression>)	=	<expression></expression>

Values

(first arm rotation information), F2 (second arm rotation information).

<expression>......For axis or element setting: coordinate value.

For hand system flag setting:

1 (right-handed system) or 2 (left-handed system)

0 (no setting)

For specifies the first arm rotation information and specifies the second arm rotation information (\*1):

0, 1, -1

\*1: For details regarding the first arm and the second arm rotation information, refer to Chapter 4 "3. Point data format".

Explanation Direct format 1: Changes the value of the point data specified axis, the hand system flag, and the first arm and the second arm rotation information.

> Format 2: Changes the value of a specified element from the shift data value.

• Points where data is to be changed must be registered in advance. An error will occur if a value change is attempted at an unregistered point (where there are no coordinate values).

# **Functions**

# **Format**

- 1. LOCx (<point expression>)
- 2. LOCx (<shift expression>)

Format 2: x......1 to 4 (element setting)

**Explanation** Format 1: Acquires the value of the point data specified axis, the hand system flag, and the first arm and the second arm rotation information.

Format 2: Acquires a specified axis element from the shift data.

## SAMPLE

LOC1(P10)=A(1) ··········· Axis 1 data of P10 is changed to the array A (1) value.

LOC2(S1)=B········ Axis 2 data of S1 is changed to the B value.

Related commands Po

Point variable, shift variable

# Format

LSHIFT (<expression 1> ,<expression 2>)

Explanation Shifts the <expression 1> bit value to the left by the amount of <expression 2>. Spaces left blank by the shift are filled with zeros (0).

# SAMPLE

A=LSHIFT(&B10111011,2) ..... The 2-bit-left-shifted &B10111011 value (&B11101100) is assigned to A.

Related commands

**RSHIFT** 

Λ

В

C

D

E

F

G

Н

I

J

K

Acquires a machine reference

# **Format**

MCHREF (<axis number>)

Values

<axis number>......1 to 6

Explanation This function provides the return-to-origin or absolute-search machine reference (unit:%) for an axis specified by the <axis number>.

> This function can only be used for axes whose return-to-origin method is set to the sensor or stroke end method.

SAMPLE

A=MCHREF(1) ..... The return-to-origin machine reference of axis 1 of robot 1 is assigned to variable A.

MID\$

# **Format**

MID\$ (<character string expression>,<expression 1>[,<expression 2>])

Values

<expression 1>......1 to 255 <expression 2>...... 0 to 255

Explanation This function extracts a character string of a desired length (number of characters) from the character string specified by <character string expression>. <expression 1> specifies the character where the extraction is to begin, and <expression 2> specifies the number of characters to be extracted.

> An error will occur if the <expression 1> and <expression 2> values violate the permissible value ranges.

> If <expression 2> is omitted, or if the number of characters to the right of the character of <expression 1> is less than the value of <expression 2>, then all characters to the right of the character specified by <expression 1> will be extracted. If <expression 1> is longer than the character string, MID\$ will be a null string (empty character string).

#### SAMPLE

B\$=MID\$(A\$,2,4) ..... The 2nd to 4th characters to the 5th char.) of A\$ are assigned to B\$.

Related commands

LEFT\$, RIGHT\$

Outputs a specified value to the MO port (internal output)

• For details regarding bit definitions, see Chapter 3 "10 Bit Settings".

# **Format**

- 1.  $MOm([b, \cdot \cdot \cdot, b]) = \langle expression \rangle$
- 2.  $MO(mb, \cdot \cdot \cdot , mb) = \langle expression \rangle$

Values

m: port number ......2 to 7, 10 to 17, 20 to 27, 30 to 37 b: bit definition ......0 to 7 <expression>.....The integer-converted lower bits corresponding to the bit definition specified at the left side are valid.

Explanation Outputs a specified value to the MO port.

In order to maintain the sensor status and axis HOLD status at each axis, ports "30" to "37" cannot be used as output ports (these ports are for referencing only). (ports 32, 33, 36, and 37 are reserved by the system)

If multiple bits are specified, they are expressed from the left in descending order (large to small).

If the [b,...,b] data is omitted, all 8 bits are processed.

• Ports "30", "31", "34", and "35" outputs

Bit	7	6	5	4	3	2	1	0
Port 30	Axis 8	Axis 7	Axis 6	Axis 5	Axis 4	Axis 3	Axis 2	Axis 1
Port 31	Axis 16	Axis 15	Axis 14	Axis 13	Axis 12	Axis 11	Axis 10	Axis 9
	Origin	sensor st	tatus 0: Of	N; 1: OFF	(Axis 1 is	not conne	cted)	
Port 34	Axis 8	Axis 7	Axis 6	Axis 5	Axis 4	Axis 3	Axis 2	Axis 1
Port 35	Axis 16				Axis 12			Axis 9
		-	-		D (Axis 1 i	-	nected)	



• For details regarding MO ports "30" to "37", see Chapter 3 "9.5 Internal output variable".

SAMPLE
MO2()=&B10111000 MO (27, 25, 24, 23) are turned
ON, and MO (26, 22, 21, 20)
are turned OFF.
$MO2(6,5,1) = \&B010 \cdots MO(25)$ are turned ON, and MO
(26, 21) are turned OFF.
MO3() = 15 ····· MO (33, 32, 31, 30) are turned
ON, and MO (37, 36, 35, 34)
are turned OFF.
MO(37,35,27,20) = A The contents of the 4 lower
bits acquired when variable
A is converted to an integer
are output to MO (37, 35, 27,
20), respectively.

Related commands

RESET, SET

# **MOTOR**

Controls the motor power status.

Format	
MOTOR	

ON OFF

PWR

Explanation This function controls the motor power on/off. The servo on/off of all robots can also be controlled at the same time.

- ON .......... Turns on the motor power. All robot servos are also turned on at the
- OFF.....Turns off the motor power. All robot servos are also turned off at the same time to apply the dynamic brake. For the axis with the brake, the brake is applied to lock it.
- PWR ...... Turns on only the motor power.

# SAMPLE

MOTOR ON ..... Turns on the motor power and all robot servos.

Format		
MOVE [ <robot number="">] (<axis< th=""><th>setting&gt;)   PTP   , <point< th=""><th>definition&gt;,option ,option</th></point<></th></axis<></robot>	setting>)   PTP   , <point< th=""><th>definition&gt;,option ,option</th></point<>	definition>,option ,option
	P	
	L	
	C	
	J	

Explanation Executes absolute movement of the axis specified to a specified robot.

It is not enabled for axes of other robots or for auxiliary axes.

A robot numbers from 1 to 4 specifies a robot. If the robot number is omitted, robot 1 is specified. If the robot number is omitted, do not describe [], either.

Example: MOVE P, P0 Specifies robot 1.

Axis specifications from 1 to 6 specify axes (multiple axes specifiable). If the axis specification is omitted, all axes are specified.

• Movement type: PTP, linear interpolation, circular interpolation Merged PTP.

• Point data setting: Direct coordinate data input, point definition.

Speed setting, arch motion setting, STOPON condition setting, • Options : CONT setting, acceleration setting, deceleration setting, plane coordinate setting, port output setting (multiple ports outputs

specifiable).

The option can be omitted.

Options	PTP	Merged PTP	Linear interpolation	Arch interpolation	Remarks
Speed setting (SPEED)	0	0	0	0	Enabled only for specified MOVE statement
Speed setting (VEL)	×	X	0	0	Enabled only for specified MOVE statement
Arch motion	0	0	×	×	Enabled only for specified MOVE statement
STOPON condition setting	0	0	0	×	Enabled only by program execution
CONT setting	0	0	0	0	Enabled only for specified MOVE statement
Acceleration setting	0	0	0	×	Enabled only for specified MOVE statement
Deceleration setting	0	0	0	×	Enabled only for specified MOVE statement
Plane coordinate setting	X	×	×	0	Enabled only for specified MOVE statement
Port output setting	×	×	0	0	Enabled only for specified MOVE statement

**MOVE** 

# Movement type

# PTP (point-to-point) movement

movement path of the axes is not guaranteed.

Execution START condition: Movement of all specified axes is complete (within the tolerance range). Execution END condition: All specified axes have entered the OUT position range. When two or more axes are specified, they will reach their target positions simultaneously. The

# Caution regarding commands which follow the MOVE P command:

If the next command following the MOVE P command is an executable command such as a signal output command, that next command will start when the movement axis enters the OUT position range. In other words, that next command starts before the axis arrives within the target position tolerance range.

### Example:


Signal output (DO, etc.)	Signal is output when axis enters within OUT position range.
DELAY	DELAY command is executed and standby starts, when axis enters the OUT position range.
HALT	Program stops and is reset when axis enters the OUT position range. Therefore, axis movement also stops.
HALTALL	All programs in execution stop when axis enters the OUT position range, task 1 is reset, and other tasks terminate. Therefore, the movement also stops.
HOLD	Program temporarily stops when axis enters the OUT position range. Therefore, axis movement also stops.
HOLDALL	All programs in execution temporarily stop when axis enters the OUT position range. Therefore, the movement also stops.
WAIT	WAIT command is executed when axis enters the OUT position range.


The WAIT ARM statements are used to execute the next command after the axis enters the tolerance range.



• The OUT position value is specified by parameter setting. This value can be changed from within the program by using the OUTPOS command.

#### **MOVE** command





7-92 Chapter 7 Robot Language Lists


### SAMPLE


MOVE P,P0..... The main robot axis robot 1 moves from its current position to the position specified by P0. (the same occurs for MOVE PTP, P0).



• PTP movement is faster than interpolation movement, but when executing continuous movement to multiple points, a positioning stop occurs at each point.

### **MOVE** command






33824-R7-00

# SAMPLE

MOVE L,P0,P1..... The robot 1 moves from its current position to the position specified by P0, P1.

### SAMPLE:MOVE L



33810-R7-00

# A

В

C

G

Н

J

M

## Circular interpolation movement

Execution START condition: Movement of all specified axes is complete (within the tolerance range). Execution END condition: Movement of all specified axes has begun.

### Execution of the immediately following command occurs immediately after axis movement begins.

When executing linear or circular interpolation in a continuous manner, the 2 movement paths are linked by connecting the deceleration and acceleration sections, enabling continuous movement without intermediate stops.

All movement axes arrive at the same time.

In circular interpolation, an arc is generated based on 3 points: the current position, an intermediate position, and the target position. **Therefore, circular interpolation must be specified by an even number of points.** 


#### Caution regarding commands which follow a MOVE C command:


If the next command following the MOVE C command is an executable command such as a signal output command, that next command will start immediately after axis movement begins. Example:

Signal output (DO, etc.)	Signal is output immediately after movement begins.
DELAY	DELAY command is executed and standby starts immediately after movement begins.
HALT	Program stops and is reset immediately after movement begins. Therefore, axis movement also stops.
HALTALL	All programs in execution stop when axis enters the OUT position range, task 1 is reset, and other tasks terminate. Therefore, the movement also stops.
HOLD	Program temporarily stops immediately after movement begins. Therefore, axis movement also stops.
HOLDALL	All programs in execution temporarily stop when axis enters the OUT position range. Therefore, the movement also stops.
WAIT	WAIT command is executed immediately after movement begins.

The WAIT ARM statement are used to execute the next command after the axis enters the tolerance range.

#### **MOVE** command






33825-R7-00

MOVE L, P20 ······· Linear movement occurs from the current position to P20.

MOVE C, P21, P22, P23, P20 ·· Arc movement occurs through points P21, P22, P23, P20.

MOVE L, P24 ····· Linear movement occurs to P24.

### SAMPLE:MOVE C



33811-R7-00



- In continuous interpolation operations, too, there are no stops at intermediate points. However, the maximum speed is slower than the PTP speed.
- Circular interpolation is possible within the following range: radius 1.00mm to 5,000.00mm.
- Circle distortion may occur, depending on the speed, acceleration, and the distance between points.
- On robots with an R-axis, the R-axis speed may become too fast and cause an error, depending on the R-axis movement distance.
- If a DELAY statement is executed after a MOVE L command, a DELAY timer is activated after the MOVE L command is executed. Therefore, if a DELAY is desired after reaching the target point, use the WAIT ARM statement after the MOVE statement.


The same applies for other commands such as HALT, etc.

- On "Multi" type robots, the "5.37: Specification mismatch" error will occur, and circular interpolation will be disabled.
- If the direction changes at an acute angle during interpolation movement, the acceleration/deceleration speed of the connection section may become too fast, causing an error. In this case, specify a slower acceleration/deceleration speed at the connection section, or use the WAIT ARM command to revise the operation pattern.


**MOVE** 

### Movement command types and the corresponding movement


### 1. PTP movement



#### 2. WAIT ARM



### 3. STOPON conditional expression



- 1) If a DELAY statement is executed after an interpolation operation, a DELAY timer is activated immediately after the movement starts. Therefore, if a DELAY is desired after reaching the target point, use the WAIT ARM statement after the MOVE command.
- 2) A deceleration and stop occurs at an intermediate point if the condition specified by the STOPON conditional expression is met (for details, see the "STOPON Condition Setting" item).

33703-R9-00

### Point data setting types

Direct numeric value input



PTP Merged PTP Linear interpolation Circular interpolation

• If both integers and real numbers are used together (mixed), all coordinate values will be handled in "mm/deg" units.



# CAUTION

- When performing linear interpolation with a hand system flag specified, be sure that the same hand system is used at the current position and target position. If the same hand system is not used, an error will occur and robot movement will be disabled.
- When performing a linear interpolation, the current position's first arm and second arm rotation information must be the same as the movement destination's first arm and second arm rotation information. If the two are different, an error will occur and movement will be disabled.

#### **Format**

p1 p2 p3 p4 p5 p6 [f] [f1] [f2]

Values p1 to p6 ......Space-separated coordinate values for each axis.

> f ......Hand system flag (SCARA robot only) f1 ......First arm rotation information (YK500TW model only).

# **Explanation**

Directly specifies coordinate values by a numeric value. If an integer is used, this is interpreted as "pulse" units, and if a real number (with decimal point) is used, this is interpreted as "mm/deg" units, with movement occurring accordingly. If both integers and real numbers are used together (mixed), all coordinate values will be handled in "mm/deg" units.

The types of movements in which this specification is possible are the PTP movement, the merged PTP movement, and the linear interpolation movement.

Hand system flags can be specified for SCARA robots when directly specifying the coordinate values in "mm" units.

To specify an extended hand system flag for SCARA robots, set either 1 or 2 at "f". If a number other than 1 or 2 is set, or if no number is designated, 0 will be set to indicate that there is no hand system flag.

- 1: Right-handed system is used to move to a specified position.
- 2: Left-handed system is used to move to a specified position.

Direct numeric value inputs can be used to set the first arm and the second arm rotation information (\*1) only on YK500TW model robots where the coordinate system-of-units has been set as "mm".

To set extended the first arm and the second arm rotation information at the YK500TW model robot, a "-1", "0", or "1" value must be specified at f1 and f2. Any other value, or no the first arm and the second arm rotation information at all, will be processed as "0".

- 0: Indicates arm rotation information where movement to the "0" position has been specified.
- 1: Indicates arm rotation information where movement to the "1" position has been specified.
- -1: Indicates arm rotation information where movement to the "-1" position has been specified.
- \*1: For details regarding the first arm and the second arm rotation information, refer to Chapter 4 "3. Point data format".

.....



 At SCARA robots with a hand system flag set in the movement destination's coordinate data, the specified hand system will have priority over the current arm type or LEFTY/RIGHTY setting.

.....

#### SAMPLE

.....

MOVE P,10000 10000 1000 1000 0 0

·····PTP movement occurs current position specified position.

MOVE • 7-97

D



# CAUTION

• When moving the robot by linear or circular interpolation to a point where a hand system flag is specified, be sure that the same hand system is used at both the current and target positions. If the same hand system is not used, an error will occur and robot movement will be disabled.





#### CAUTION

• When performing a linear and circular interpolation, the current position's first arm and second arm rotation information must be the same as the movement destination's first arm and second arm rotation information. If the two are different, an error will occur and movement will be disabled.

Point definition



PTP Merged PTP (linear interpolation) Circular interpolation

### **Format**

<point expression>[,<point expression>...]

**Explanation** 

Specifies a <point expression>. Two or more data items can be designated by separating them with a comma (,).

Circular interpolation must be specified by an even number of points.

 At SCARA robots with a hand system flag set in the movement destination's coordinate data, the specified hand system will have priority over the current arm type or LEFTY/RIGHTY setting.

#### SAMPLE

MOVE ..... Moves from the current position to the position specified by P1.

MOVE P, P20, P0, P100 ····· Moves in sequence from the current position to positions specified by P20, P0, P100.

D

## Option types

PTP Merged PTP (linear interpolation) Circular interpolation) Speed setting 1

#### **Format**

- SPEED = <expression> 1.
- 2.  $S = \langle expression \rangle$

<expression>......1 to 100 (units: %)

# **Explanation**

The actual speed will be as follows:

Specifies the program speed in an <expression>.

• [Robot max. speed (mm/sec)] × [automatic movement speed (%)] × [program movement speed (%)].

This option is enabled only for the specified MOVE statement.

## SAMPLE

MOVE P, P10, S=10 ····· Moves from the current position to the position specified by P10, at 10% of the program movement speed.

PTP Merged PTP (linear interpolation) Circular interpolation Speed setting 2

#### **Format**

VEL = <expression>

Values <expression>......For SCARA robot: 1 to 750

For XY robot: 1 to 1000 (units: mm/sec)

**Explanation** Specifies the maximum composite speed (in "mm/sec" units) of the XYZ axes in an <expression>. This option is specifiable when the robot is a SCARA robot or an XY robot and the type of movement is linear interpolation and circular interpolation movements.

This option is enabled only for the specified MOVE statement.

#### SAMPLE

MOVE L, P10, VEL=100 ······ Moves from the current position to the position specified by P10 at the maximum composite speed of 100 mm/sec. of the XYZ attribute axis.

This option specifies only the maximum speed and does not guarantee movement at the specified speed.

• This option specifies only the maximum composite speed and does not guarantee movement at the specified speed.

Values

x ......Specifies an axis from A1 to A6.

<expression>......An integer value is processed in "pulse" units.

A real number (with decimal point) is process in "mm/ deg" units.

<expression 1>, <expression 2>...An integer value is processed in "pulse" units.

A real number (with decimal point) is process in "mm/ deg" units.

**MOVE** 

- When there is a real value in any of the <expression>, <expression 1>, and <expression 2>, all expressions are handed as real value.
- The <expression 1> and <expression 2> are optional. These expressions specify the arch distance 1 and arch distance 2, respectively.



The axis arch distance parameters can be changed using ARCHP1/ ARCHP2. The smaller the value, the shorter the movement execution time.



- 1. The "x" specified axis begins moving toward the position specified by the <expression> (see "1" in the Fig. below).
- 2. When the axis specified by "x" moves the arch distance 1 or more, other axes move to their target positions ("2" shown in the figure below).
- 3. The axis specified by "x" moves to the target position so that the remaining movement distance becomes the arch distance 2 when the movement of other axes is completed ("3" shown in the figure below).
- 4. The command ends when all axis enter the OUT position range.

This option can be used only for PTP movement and merged PTP movement. When the axis specified by "x" is the first arm or second arm of the SCARA robot or the axis 1 or axis 2 of the XY robot, the <expression> and target position value are limited to an integer (pulse units).

<expression> value: SCARA and XY type robots.

Target position value: SCARA type robot.


The values are indicated as the motor position rather than the coordinate values.

## SAMPLE

MOVE P, P1, A3=0(150, 100) ······The A3-axis moves from the

current position to the "0 pulse" position. After that, other axes move to P1. Finally, the A3-axis moves to P1.

#### SAMPLE:MOVE A3



33704-R9-00



• STOPON condition setting (PTP) Merged PTP (linear interpolation) (Circular interpolation)

### **Format**

STOPON < conditional expression>

### **Explanation**

Stops movement when the conditions specified by the conditional expression are met. Because this is a deceleration type stop, there will be some movement (during deceleration) after the conditions are met.

If the conditions are already met before movement begins, no movement occurs, and the command is terminated.

This option can only be used for PTP movement and linear interpolation movement.

This option is only possible by program execution.

### SAMPLE

MOVE P, P100, STOPON DI (20) = 1

..... Moves from the current position to the position specified by P100. If the "DI (20) = 1" condition is met during movement, a deceleration and stop occurs, and the next step is then executed.



• When the conditional expression used to designate the STOPON condition is a numeric expression, expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

**MOVE** 

# NOTE

- •The CONT setting can be used to reduce the PTP movement START positioning time.
- The path to the target point is not guaranteed.

# **Format**

CONT setting

CONT

### **Explanation**


When movement is executed with CONT setting option, when all movable axes enter the OUT position range (with the command being terminated at that point), will begin movable axes to complete their movement into the tolerance range. This option is enabled only for the specified MOVE statement.


### SAMPLE

MOVE P, P10, P11, CONT

..... Moves from the current position to the position specified by P10, and then moves to P11 without waiting for the moving axes to arrive in the tolerance range.

# **SAMPLE:MOVE CONT**





33814-R7-00

● Acceleration setting PTP Merged PTP linear interpolation Circular interpolation

**Format** 

 $ACC = \langle expression \rangle$ 

Values <expression>......1 to 100 (units: %)

Explanation Specifies the robot acceleration rate in an <expression>. The actual robot acceleration is determined by the acceleration coefficient parameter setting. This option can be used only for linear interpolation movement and is enabled only for the specified MOVE statement.

SAMPLE

MOVE L,P100,ACC=10 ...... Moves at an acceleration rate of 10% from the current position to the position specified by P100.

**Format** 

DEC = <expression>

Values <expression>......1 to 100 (units: %)

Explanation Specifies the robot deceleration rate in an <expression>. The actual robot deceleration is determined by the acceleration coefficient parameter setting (the setting is specified as a percentage of the acceleration setting value (100%)).

This option can be used only for linear interpolation movement and is enabled only for the specified MOVE statement.

SAMPLE

MOVE L,P100,DEC=20 .... Moves at a deceleration rate of 20% from the current position to the position specified by P100.

A

В

C

D

E

F

G

L

K

Ь

M

**NOTE** 

3-dimensional circle.

plane.

•If no coordinate

plane is specified, the robot moves along a

• When a 2-axis robot is used, the robot moves along a circle on the XY

**MOVE** 

**Format** ΧY YZ

Values XY.....XY coordinate plane YZ......YZ coordinate plane ZX.....ZX coordinate plane

#### **Explanation**

ZX

Coordinate plane setting

When circular interpolation is executed by setting coordinates, this option executes circular interpolation so that the projection on the specified coordinate plane becomes a circle.

This option can be used for circular interpolation movement and is enabled only for the specified MOVE statement.

SAMPLE
P10 = 100.00 100.00 20.00 0.00 0.00 0.00
P11 = 150.00 100.00 0.00 0.00 0.00 0.00
P12 = 150.00 150.00 20.00 0.00 0.00 0.00
P13 = 100.00 150.00 40.00 0.00 0.00 0.00
MOVE P,P10
MOVE C, P11, P12
MOVE C, P13, P10 Moves continuously along a
3-dimensional circle generated
at P10, P11, P12, and P12,
P13, P10.
MOVE C, P11, P12, XY
MOVE C, P13, P10, XY ······ Moves continuously along a
circle on an XY plane generated
at P10, P11, P12, and P12,
P13, P10. Z-axis moves to the
position specified by P12 and P10
(the circle's target position).

#### Port output setting (PTP) (Merged PTP) (linear interpolation) (Circular interpolation)

#### Format 1

DO	$ m([b, \dots, b]) = @$	2>
MO SO		
SO		

#### Format 2

DO	$ (mb, \cdots, mb)  = @$	
MO		
SO		

Values

m: port number ......2 to 7, 10 to 17, 20 to 27

b: bit definition ......0 to 7

<expression 1>......Value which is output to the specified port (only

integers are valid).

<expression 2>......Position where the port output occurs. This position can be specified in "mm" units down to the 2nd

decimal position.



Output to ports "0" and "1" is not allowed at DO, MO, and SO.



• For bit setting details, see Chapter 3 "10 Bit Settings".

**Explanation** 

During linear interpolation or circular interpolation movement, this command option outputs the value of <expression 1> to the specified port when the robot reaches the <expression 2> distance (units: "mm") from the start position.

The <expression 2> numeric value represents a circle radius centered on the movement START point.

This command option can only be used with linear or circular interpolation movement, and it can be specified no more than 2 times per MOVE statement. If multiple bits are specified, they are expressed from the left in descending order (large to small).

If the [b,...,b] data is omitted in format 1, all 8 bits are processed.

If no hardware port exists, nothing is output.

#### SAMPLE 1

```
MOVE P, P0
MOVE L, P1, DO2()=105@25.85
      ...... During linear interpolation movement to P1,
                 105 (&B01101001) is output to DO2() when the
                 robot reaches a distance of 25.85mm from PO.
```

# SAMPLE 2

```
A!=10
B! = 20
MOVE L, P2, MO(22) = 1@A!, MO(22) = 0@B!
      ...... After movement START toward P2, MO(22)
                switches ON when the robot has moved a
                distance of 10mm, and switches OFF when
                the robot has moved a distance of 20mm.
```

Related commands

MOVEI, DRIVE, DRIVEI, WAIT ARM

MOVE 7-105

D

Performs relative movement of all robot axes

#### **Format**

,<point definition> [, option [, option]...] MOVEI Ρ

**Explanation** Executes relative position movement commands for the robot.

MOVEI is used for all specified axes.

It is not enabled for other groups, or for auxiliary axes.

 Movement type : PTP

• Point data setting: Direct coordinate data input, point definition.

• Options : Speed setting

MEMO

• If the MOVEI statement is interrupted and then re-executed, the movement target position can be selected at the "MOVEI/DRIVEI start position" setting in the controller. For details, refer to the controller user's manual.

1) KEEP (default setting) Continues the previous (before interruption) movement. The original

target position remains unchanged.

2) RESET Relative movement begins anew from the current position. The new

target position is different from the original one (before interruption).

(Backward compatibility)

#### Movement type

#### PTP (point-to-point) movement

Execution START condition: Movement of all specified axes is complete (within the tolerance range).

Execution END condition: All specified axes have entered the OUT position range.

When two or more axes are specified, they will reach their target positions simultaneously. The movement path of the axes is not guaranteed.

#### Caution regarding commands which follow the MOVEI command:


If the next command following the MOVEI command is an executable command such as a signal output command, that next command will start when the movement axis enters the OUT position range. In other words, that next command starts before the axis arrives within the target position tolerance range.


Example:

Signal output (DO, etc.)	Signal is output when axis enters within OUT position range.				
DELAY	DELAY command is executed and standby starts, when axis enters the OUT position range.				
HALT	Program stops and is reset when axis enters the OUT position range. Therefore, axis movement also stops.				
HALTALL	All programs in execution stop when axis enters the OUT position range, task 1 is reset, and other tasks terminate. Therefore, the movement also stops.				
HOLD	Program temporarily stops when axis enters the OUT position range. Therefore, axis movement also stops.				
HOLDALL	All programs in execution temporarily stop when axis enters the OUT position range. Therefore, the movement also stops.				
WAIT	WAIT command is executed when axis enters the OUT position range.				

The WAIT ARM statement are used to execute the next command after the axis enters the tolerance range.

#### **MOVEI** command





33826-R7-00

# SAMPLE

MOVEI P,P0 ..... From its current position, the main robot axis moves (PTP movement) the amount specified by P0.

В

D

E

F

J

K

# Point data setting types

#### Direct numeric value input


### PTP

#### Format

p1 p2 p3 p4 p5 p6 [f] [f1] [f2]

# NOTE

 If both integers and real numbers are used together (mixed), all coordinate values will be handled in "mm/deg" units.



### **Explanation**

Directly specifies coordinate values by a numeric value. If an integer is used, this is interpreted as "pulse" units, and if a real number is used, this is interpreted as "mm/deg" units, with movement occurring accordingly.

Hand system flags can be specified for SCARA robots when directly specifying the coordinate values in "mm" units.

To specify an extended hand system flag for SCARA robots, set either 1 or 2 at "f". If a number other than 1 or 2 is set, or if no number is designated, 0 will be set to indicate that there is no hand system flag.

- 1: Right-handed system is used to move to a specified position.
- 2: Left-handed system is used to move to a specified position.

Direct numeric value inputs can be used to set the first arm and the second arm rotation information (\*1) only on YK500TW model robots where the coordinate system-of-units has been set as "mm".

To set extended the first arm and the second arm rotation information at the YK500TW model robot, a "-1", "0", or "1" value must be specified at f1 and f2. Any other value, or no the first arm and the second arm rotation information at all, will be processed as "0".

- 0: Indicates arm rotation information where movement to the "0" position has been specified.
- 1: Indicates arm rotation information where movement to the "1" position has been specified.
- -1: Indicates arm rotation information where movement to the "-1" position has been specified.
- \*1: For details regarding the first arm and the second arm rotation information, refer to Chapter 4 "3. Point data format".



• At SCARA robots with a hand system flag set in the movement destination's coordinate data, the specified hand system will have priority over the current arm type or LEFTY/RIGHTY setting.

#### SAMPLE

MOVEI P, 10000 10000 1000 1000 0 0

..... From its current position, the axis moves (PTP movement) the specified amount (pulse units).

7 100 Ch

7-108 Chapter 7 Robot Language Lists

60

<point expression>[,<point expression>...]

**Explanation** Specifies a <point expression>. Two or more data items can be designated by separating them with a comma ( , ).

• At SCARA robots with a hand system flag set in the movement destination's coordinate data, the specified hand system will have priority over the current arm type or LEFTY/RIGHTY setting.

.....

SAMPLE

MOVEI P,P1 ..... From its current position, the axis moves (PTP movement) the amount specified by P1.

В

C

D

E

F

K

• This option specifies only

specified speed.

the maximum speed

and does not guarantee movement at the

# Option types

#### Speed setting

# PTP

#### Format

- 1. SPEED = <expression>
- 2.  $S = \langle expression \rangle$

Values <expression> ......1 to 100 (units: %)

The actual speed will be as follows:

Specifies the program speed in an <expression>.

• [Robot max. speed (mm/sec)] × [automatic movement speed (%)] × [program movement speed (%)].

This option is enabled only for the specified MOVEI statement.

#### SAMPLE

**Explanation** 

MOVEI P,P10,S=10 ..... From its current position, the axis moves (PTP movement) the amount specified by P1, at 10% of the program movement speed.

Related commands MOVE, DRIVE, DRIVEI, WAIT ARM

В

C

D

E

F

G

Œ

J

K

L

Sets a specified communication port to the "offline" mode

		- 1
120	100	nat

OFFLINE	[	ETH	]
	[	CMU	]

Values

<expression>.....ETH, CMU, or no setting

Explanation Changes the communication mode parameter in order to switch the communication mode to OFFLINE.

> ETH.....Changes the Ethernet communication mode parameter to OFFLINE and clears the transmission and reception buffers. CMU ......Changes the RS-232C communication mode parameter to OFFLINE, resets the communication error, and clears the reception buffer.

> No setting......Changes the Ethernet and RS-232C communication mode parameter to OFFLINE and clears the transmission and reception buffers.

SAMPLE

OFFLINE

SEND CMU TO A\$

SEND CMU TO P10

ONLINE

HALT

# ON ERROR GOTO

Jumps to a specified label when an error occurs

#### **Format**

- 1. ON ERROR GOTO < label>
- 2. ON ERROR GOTO 0

Values

Error output information...... ERR: Error code number

ERL: Line number where error occurred

Explanation Even if an error occurs during execution of the robot language, this statement allows the program to jump to the error processing routine specified by the <label>, allowing the program to continue without being stopped (this is not possible for some serious

> If "0" is specified instead of the <label>, the program stops when an error occurs, and an error message displays.

> If ON ERROR GOTO "0" is executed at any place other than an error processing routine, the ON ERROR GOTO command is canceled (interruption canceled).

> The error processing routine can process an error using the RESUME statement and the error output information (ERR, ERL).



- If a serious error such as "17.4: Overload" occurs, the program execution stops.
- The most recently executed "ON ERROR GOTO < label>" statement is valid.
- If an error occurs during an error processing routine, the program will stop.
- "ON ERROR GOTO <label>" statements cannot be used within error processing routines.

#### SAMPLE

ON ERROR GOTO \*ER1

FOR A = 0 TO 9

P[A+10] = P[A]

NEXT A

\*L99: HALT

' ERROR ROUTINE

\*ER1:

IF ERR = &H0604 THEN \*NEXT1......Checks to see if "Point doesn't exist"

error has occurred.

IF ERR = &H0606 THEN \*NEXT2.....Checks to see if "Subscript out of range"

error has occurred.

ON ERROR GOTO 0 ..... Displays the error message and

stops the program.

\*NEXT1:

RESUME NEXT·····Jumps to the next line after the error line and resumes

program execution.

\*NEXT2:

RESUME \*L99 ····· Jumps to label \*L99 resumes program execution.

RESUME

Related commands

7-112 Chapter 7 Robot Language Lists

Executes the subroutine specified by the <expression> value

```
Format
```

```
ON<expression>GOSUB<label 1> [,<label 2>...]
            * GOSUB can also be expressed as "GO SUB".
```

Values

<expression>.....0 or positive integer

Explanation The <expression> value determines the program's jump destination.

An <expression> value of "1" specifies a jump to <label 1>, "2" specifies a jump to <label 2>, etc.

Likewise, (<expression> value "n" specifies a jump to <label n>.)

If the <expression> value is "0" or if the <expression> value exceeds the number of existing labels, no jump occurs, and the next command is executed.

After executing a jump destination subroutine, the next command after the ON to GOSUB statement is executed.

```
SAMPLE
```

```
' MAIN ROUTINE
*ST:
ON DI3() GOSUB *SUB1, *SUB2, *SUB3 ··· *SUB1 to *SUB3 are
                                  executed.
GOTO *ST ..... Returns to *ST.
HALT
' SUB ROUTINE
*SUB1:
  MOVE P, P10, Z=0
  RETURN
*SUB2:
  DO(30) = 1
  RETURN
*SUB3:
  DO(30) = 0
  RETURN
```

Related commands

GOSUB, RETURN

**Format** 

ON<expression>GOTO<label 1> [, <label 2>...] \* GOTO can also be expressed as "GO TO".

Values

<expression>.....0 or positive integer

**Explanation** The <expression> value determines the program's jump destination.

An <expression> value of "1" specifies a jump to <label 1>, "2" specifies a jump to <label 2>, etc.

Likewise, (<expression> value "n" specifies a jump to <label n>.)

If the <expression> value is "0" or if the <expression> value exceeds the number of existing labels, no jump occurs, and the next command is executed.

```
SAMPLE
```

```
' MAIN ROUTINE
```

\*ST:

ON DI3() GOTO \*L1, \*L2, \*L3.....Jumps to \*L1 to \*L3 in accordance with the DI3() value.

GOTO \*ST .....Returns to \*ST.

HALT

' SUB ROUTINE

\*L1:

MOVE P, P10, Z=0

GOTO \*ST

\*L2:

DO(30) = 1

GOTO \*ST

\*L3:

DO(30) = 0

GOTO \*ST

Related commands

GOTO

Sets the specified communication port to the "online" mode

Ea	-	
ГΟ	ш	nat

ONLINE	[]	ETH	]
	[	CMU	]

Values

<expression>.....ETH, CMU, or no setting

Explanation Changes the communication mode parameter in order to switch the communication mode to ONLINE.

> ETH ......Changes the Ethernet communication mode parameter to ONLINE and clears the transmission and reception buffers. CMU ......Changes the RS-232C communication mode parameter to ONLINE, resets the communication error, and clears the

> > reception buffer.

No setting......Changes the Ethernet and RS-232C communication mode parameter to ONLINE, resets the communication error, and clears the reception buffer.

SAMPLE

OFFLINE

SEND CMU TO A\$

SEND CMU TO P10

ONLINE

HALT

Q

Format

ORD (<character string expression>)

**Explanation** Acquires the character code of the first character in a <character string expression>.

SAMPLE

(=&H42) is assigned to A.

CHR\$

Related commands

Specifies/acquires the robot's return-to-origin sequence

#### **Format**

ORGORD [<robot number>] <expression>

Values

<robot number>......1 to 4

<expression>.....n to nnnnnn (n : 0 to 6)

Explanation Sets the axis sequence parameter for return-to-origin and absolute search operation of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> The 1 to 6 axes are expressed as "1 to 6" values, respectively, and the <expression> value must be 1-digit to 6-digit integer.

The same axis cannot be specified twice.

After the specified axes are returned to their origin points in sequence, from left to right, the remaining axes return to their origin points simultaneously.

If the <expression> value is "0", all axes will be returned to their origin points simultaneously.

#### **Functions**

#### **Format**

ORGORD [<robot number>]

**Values** 

<robot number>......1 to 4

Explanation Acquires the axis sequence parameter for return-to-origin and absolute search operation of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

-	-	-	7	-	r	9	۲	_
ч	7AV	ii (V,	10	D)	a		h	η,

A=3

ORGORD A ..... A return-to-origin is executed

first for axis 3.

ORIGIN ..... After the return-to-origin of axis 3 of robot 1 is completed,

a return-to-origin is executed

for the remaining axis.

MOVE P, P0

A=ORGORD ..... The main group's return-toorigin sequence parameter is

assigned to variable A.

HALT

Related commands

**ORIGIN** 

Q

# **ORIGIN**

Performs a return-to-origin

# Format

#### ORIGIN

Explanation This statement performs a return-to-origin of a robot, or an absolute search for a semiabsolute axis.

> If the movement is stopped at an intermediate point, an "incomplete return-to-origin" status will occur.

> When multiple robots are specified, the return-to-origin and absolute search are first performed for the robot 1 and then for the robots 2 to 4.

#### SAMPLE

ORIGIN

..... Performs return-to-origin.

Related commands

ORGORD, MCHREF

**Format** OUT  $DOm([b, \cdot \cdot \cdot, b])$ [, <time>]  $DO(mb, \cdot \cdot \cdot, mb)$  $MOm([b, \cdot \cdot \cdot, b])$  $MO(mb, \cdot \cdot \cdot, mb)$  $SOm([b, \cdot \cdot \cdot, b])$  $SO(mb, \cdot \cdot \cdot, mb)$  $LOO([b, \cdot \cdot \cdot, b])$ LO(0b, · · · , 0b) TO0([b, · · · ,b])  $TO(0b, \cdot \cdot \cdot, 0b)$ 

Values

m: port number ......2 to 7, 10 to 17, 20 to 27 b: bit definition ......0 to 7 <expression>......1 to 3600000 (units: ms)



Output to ports "0" and "1" are not allowed at DO, and SO.

REFERENCE

• For bit setting details, see Chapter 3 "10 Bit Settings".

Explanation This statement turns ON the specified port output and terminates the command. (The program proceeds to the next line.) Output to that port is then turned OFF after the time specified by the <expression> has elapsed. If the operation is stopped temporarily at an intermediate point and then restarted, that port's output is turned OFF when the remaining <expression> specified time has elapsed.

If this <expression> is omitted, the specified port's output remains ON.

Up to 16 OUT statements using <expressions> can be executed at the same time. Attempting to execute 17 or more OUT statements will activate error "6.26: Insufficient memory for OUT".

If multiple bits are specified, they are expressed from the left in descending order (large to small).

If no hardware port exists, nothing is output.

```
SAMPLE
 OUT DO2(),200 ..... Turns DO(27 to 20)
                                               ON,
                          turns them OFF 200ms later.
 OUT DO(37,35,27,20) ······· Turns DO(37, 35, 27, 20) ON.
```

Related commands DO, MO, SO, TO, LO

#### **Format**

OUTPOS

- 1. OUTPOS [<robot number>] <expression>
- 2. OUTPOS [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......1 to 6144000 (Unit: pulses)

Explanation) Changes the parameter's OUT position of the robot axis specified by the <robot number> to the value indicated in the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

.....

Format 1: The change is applied to all axes specified to specified robots.

Format 2: The change is applied only to the axis specified by <axis number>.

MEMO

• If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and command execution is stopped.

#### **Functions**

#### **Format**

OUTPOS [<robot number>] (<axis number>)

**Values** 

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the OUT position parameter value for the axis specified by the <expression> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

• If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and command execution is stopped.

```
SAMPLE
' CYCLE WITH DECREASING OUTPOS
DIM SAV(3)
GOSUB *SAVE_OUTPOS
FOR A=1000 TO 10000 STEP 1000
   GOSUB *CHANGE_OUTPOS
   MOVE P, P0
   DO3(0)=1
   MOVE P,P1
   DO3(0) = 0
NEXT A
GOSUB *RESTORE_OUTPOS
HALT
*CHANGE_OUTPOS:
   FOR B=1 TO 4
      OUTPOS(B) = A
   NEXT B
  RETURN
*SAVE OUTPOS:
   FOR B=1 TO 4
      SAV(B-1)=OUTPOS(B)
   NEXT B
   RETURN
*RESTORE OUTPOS:
   FOR B=1 TO 4
      OUTPOS (B) = SAV(B-1)
   NEXT B
   RETURN
```

Ν

0

P

Q

D

S

Γ

U

W

X

#### Format

PDEF(<Pallet definition number>) = <expression 1>, <expression 2> [, <expression 3>]

#### Values

<Pallet definition number>.....0 to 39

<point definition>.....The point used for a pallet definition. Continuous 5 points starting with the specified point are used.

<expression 1>.....Number of points (NX) between P[1] and P[2].

<expression 2>.....Number of points (NY) between P[1] and P[3].

<expression 3>.....Number of points (NZ) between P[1] and P[5].

Total number of points: <expression 1>  $\times$  <expression 2>  $\times$  <expression 3> must be 32767 or less.

Regarding the P[1] to P[5] definition, see the figure

below.

### **Explanation**


Defines the pallets to permit execution of the pallet movement command.

Also changes the dividing conditions of previously defined pallet data.

After specifying the number of points per axis, the equally-spaced points for each axis are automatically calculated and defined in the sequence shown in the figure below. If <expression 3> (Z-axis direction) is omitted, the height direction value becomes

The total number of points defined for a single pallet must not exceed 32,767.

### **Automatic point calculation**



33815-R7-00

## SAMPLE

PDEF (1) =P3991,3,4,2..... Pallet definition 1 is defined as 3 x 4 x 2 by using P3991 to P3995.

0

P

Q

R

S

т

U

Y

#### **Format**

PMOVE [<robot number>] (<pallet definition number> ,
<pallet position number>) [,option[,option]...]

Values

<ru><robot number>......0 to 4<pallet definition number>.....0 to 39<pallet position number>......1 to 32767

**Explanation** 

Executes a robot axis "pallet move" command. (The specified pallet numbers must be registered in advance.)

The PMOVE command applies to all main robot axes, and the PMOVE2 command applies to all sub robot axes. These commands do not apply to any other group axes, or to auxiliary axes.

• Movement type: PTP


Pallet definition number: Numeric expressionPallet position number: Numeric expression

• Options: Speed setting, arch motion setting, STOPON condition

setting

The position numbers for each pallet definition are shown below.

#### Position numbers for each pallet definition



33816-R7-00



• Acquires the XYZ attribute axes move to the position determined by calculated values, the R attribute axis moves to the position specified by pallet point data P [1].

Options	PTP	Remarks
Speed setting (SPEED)	0	Enabled only for specified PMOVE statement
Arch motion	0	Enabled only for specified PMOVE statement
STOPON condition setting	0	Enabled only by program execution

	Ы	A	ΙŲ	å	5	ш	ľ	22
_				_			_	_

PMOVE(1,16) ...... The main robot axis moves from its current position to the position specified by pallet position number 16 of pallet definition number 1.

PMOVE **7-123** 

N

0

P

Q

R

S

T

W

X

Y

**PMOVE** 

# Movement type

#### PTP (point-to-point) movement

PTP movement begins after positioning of all movement axes is complete (within the tolerance range), and the command terminates when the movement axes enter the OUT position range. Although the movement axes reach their target positions simultaneously, their paths are not guaranteed.

### Caution regarding commands which follow the PMOVE command:


If the next command following the PMOVE command is an executable command such as a signal output command, that next command will start when the movement axis enters the OUT position range. In other words, that next command starts before the axis arrives within the target position OUT position range.


#### Example:

Signal output (DO, etc.)	Signal is output when axis enters within OUT position range.
DELAY	DELAY command is executed and standby starts, when axis enters the OUT position range.
HALT	Program stops and is reset when axis enters the OUT position range. Therefore, axis movement also stops.
HALTALL	All programs in execution stop when axis enters the OUT position range, task 1 is reset, and other tasks terminate. Therefore, the movement also stops.
HOLD	Program temporarily stops when axis enters the OUT position range. Therefore, axis movement also stops.
HOLDALL	All programs in execution temporarily stop when axis enters the OUT position range. Therefore, the movement also stops.
WAIT	WAIT command is executed when axis enters the OUT position range.

The WAIT ARM statement is used to execute the next command after the axis enters the tolerance range.

#### **PMOVE** command





33827-R7-00

# **Option types**

### Speed setting

#### **Format**

- SPEED = <expression> 1.
- 2.  $S = \langle expression \rangle$

# <expression>......1 to 100 (units: %)

#### **Explanation** Specifies the program speed in an <expression>. The movement speed is the automatic movement speed multiplied by the program movement speed. This option is enabled only for the specified PMOVE statement.

# SAMPLE

```
program speed, from the current
                 position to the position specified
                 by pallet position number 3 of
                 pallet definition number 1.
```

## Arch motion setting

#### **Format**

 $x = \langle expression \rangle [, x = \langle expression \rangle ...]$ 

Values x ......Specifies the Z,R,A,B axis. <expression>.....An integer value is processed in "pulse" units. A real number (with decimal point) is process in "mm/

deg" units.

**Explanation** 

- 1. The "x" specified axis begins moving toward the position specified by the <expression>.
- 2. When the "x" specified axis enters the arch position range, all other axes move toward the target position.
- 3. When all axes other than the "x" specified axis enter the arch position range, and the "x" specified axis enters the tolerance range of the position specified by the <expression>, the "x" specified axis then moves to the target position.
- 4. The command ends when all axis enter the OUT position range.


#### SAMPLE

PMOVE (1,A), Z=0.....The Z-axis first moves from the current position to the "O pulse" position. Then the other axes move to the position specified by pallet position number A of pallet definition number 1. Finally the Z-axis moves to the position specified by pallet position number A.

This option specifies only the maximum speed and does not guarantee movement at the specified speed.

PMOVE • 7-125

# SAMPLE:PMOVE Z



33817-R7-00

#### STOPON condition setting

PTP

#### **Format**

STOPON < conditional expression>

Explanation

Stops movement when the conditions specified by the conditional expression are met. Because this is a deceleration type stop, there will be some movement (during deceleration) after the conditions are met.

If the conditions are already met before movement begins, no movement occurs, and the command is terminated.

This option is only possible by program execution.

#### SAMPLE

PMOVE(A, 16), STOPON DI(20)=1

..... Moves from the current position to the position specified by pallet position number 16 of pallet definition number A, then decelerates and stops when the condition "DI(20) = 1" is met.

**Ø** MEMO

• When the conditional expression used to designate the STOPON condition is a numeric expression, expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

N

0

P

Q

R

5

W

W

X

**NOTE** 

units.

both integers and

real numbers are used together (mixed), all

coordinate values will

be handled in "mm/deg"

#### **Format**

[LET] p1 p2 p3 p4 p5 p6[f][f1][f2]

#### Values

n	.Point number: 0 to 29999.
p1 to p6	. Point data: the range varies according to the format.
f	. Hand system flag: 1 or 2 (for SCARA robots only).
	First arm rotation information : -1, 0, 1 (YK500TW model
	only).
f2	.Second arm rotation information : -1, 0, 1 (YK500TW model
	only).

**Explanation** Defines the point data.

- 1. "n" indicates the point number.
- 2. Input data for "p1" to "p6" must be separated with a space (blank).
- 3. If all input data for "p1" to "p6" are integers (no decimal points), the movement units are viewed as "pulses". "p1" through "p6" then correspond to axis 1 through axis 6.
- 4. If there is even 1 real number (with decimal point) in the input data for "x" through "b", the movement units are recognized as "mm". In this case, "x" to "z" correspond to the x, y and z coordinates of a Cartesian coordinate system, while "r" to "b" correspond to axes 4 to 6.
- 5. The input data ranges are as follows:

For "pulse" units: -6,144,000 to 6,144,000 range For "mm" units: -99,999.99 to 99,999.99 range

Hand system flags can be specified for SCARA robots when specifying point definition data in "mm" units.

To specify an extended hand system flag for SCARA robots, set either 1 or 2 at "f". If a number other than 1 or 2 is set, or if no number is designated, 0 will be set, indicating that there is no hand system flag.

- 1: Indicates a right-handed system point setting.
- 2: Indicates a left-handed system point setting.

The first arm and the second arm rotation information (\*1) can be specified on YK500TW where point data is defined in "mm" units.

To set extended the first arm and the second arm rotation information at the YK500TW model robot, a "-1", "0", or "1" value must be specified at f1 and f2. Any other value, or no the first arm and the second arm rotation information at all, will be processed as "0".

- 0: Indicates arm rotation information where "0" has been specified.
- 1: Indicates arm rotation information where "1" has been specified.
- -1: Indicates arm rotation information where "-1" has been specified.
- \*1: For details regarding the first arm and the second arm rotation information, refer to Chapter 4 "3. Point data format".

73

Pn



# NOTE

- All input values are handled as constants.
- •If controller power is turned off during execution of a point definition statement, a memory-related error such as "9.2: Point checksum error" may occur.

# SAMPLE

```
P1 =
            0
                    0
                            0
                                     0
                                              0
                                                      0
      100.00 200.00
                        50.00
                                          0.00
                                                   0.00
P2 =
                                  0.00
       10.00
P3 =
                 0.00
                         0.00
                                  0.00
                                          0.00
                                                   0.00
P10= P2
FOR A=10 TO 15
   P[A+1] = P[A] + P3
NEXT A
FOR A=10 TO 16
   MOVE P, P1, P[A]
NEXT A
HALT
```

Related commands

Point assignment statement (LET)

P

G

R

S

Т

П

V

W

X

# **Format**

PPNT(pallet definition number, pallet position number)

**Explanation** Creates the point data specified by the pallet definition number and the pallet position number.

# SAMPLE

P10=PPNT(1,24) ...... Creates, at P10, the point data specified by pallet position number 24 of pallet definition number 1.

Related commands PDEF, PMOVE

N

0

P

Q

\_

ς

Т

U

**A**/

Χ

Y

Displays the specified expression value at the programming box

## **Format**

PRINT

[<expression][|, | <expression>...][|

Values

<expression>.....character string, numeric value, variable.

**Explanation** Displays a specified variable on the programming box screen.

Output definitions are as follows:

- 1. If numbers or character strings are specified in an <expression>, they display as they are. If variables or arrays are specified, the values assigned to the specified variables or arrays display.
- 2 If no <expression> is specified, only a line-feed occurs.
- 3. If the data length exceeds the screen width, a line-feed occurs, and the data wraps to the next line.
- 4. If a comma (, ) is used as a display delimiter, a space (blank) is inserted between the displayed items.
- 5. If a semicolon (;) is used as a display delimiter, the displayed items appear in succession without being separated.
- 6. If the data ends with a delimiter, the next PRINT statement is executed without a line-feed. When not ended with a display delimiter, a line-feed occurs.

• Data communication to the programming box screen occurs in order for the PRINT statement to be displayed there. Therefore, program execution may be delayed when several PRINT statements are executed consecutively.

#### SAMPLE

PRINT A Displays the value of variable A. PRINT "A1 ="; A1 ..... Displays the value of variable A1 after "A1 =". PRINT "B(0), B(1) = "; B(0); ", "; B(1)PRINT P100 ..... Displays the P100 value.

Related commands

**INPUT** 

Specifies/acquires a pushing thrust parameter.

#### **Format**

- 1. PSHFRC [<robot number>] <expression>
- 2. PSHFRC [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>.....-1000 to 1000 (unit: %)

Explanation Changes the pushing thrust parameter of the robot axis specified by the <robot number> to the value of <pushing thrust>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> If the F option is omitted in the PUSH statement, the pushing control is executed with the setting of the pushing thrust parameter.

Actual pushing thrust is as follows.

• Rated thrust x <pushing thrust>/100

In format 1, the change occurs at all axes.

In format 2, the change occurs at parameter of the axis specified by the <axis number>.

#### SAMPLE

PSHFRC (1) = 10 ····· Changes the pushing thrust parameter of axis 1 of robot 1 to 10%

### **Functions**

#### **Format**

PSHFRC [<robot number>] (<axis number>)

**Values** 

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the value of pushing thrust parameter of the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

#### SAMPLE

A=PSHFRC (1) ..... The pushing thrust parameter of axis 1 of robot assigned to variable A.

# 77

Specifies/acquires a pushing detection speed threshold parameter.

#### **Format**

**PSHJGSP** 

- 1. PSHJGSP [<robot number>] <expression>
- 2. PSHJGSP [<robot number>] (<axis number>) = <expression>

### Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......0: Invalid, 1 to 100 (units: %)

Explanation Changes the pushing detection speed threshold parameter of the robot axis specified by the <robot number> to the value indicated in the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> If the pushing detection speed threshold parameter is enabled, a pushing operation is detected only when the movement speed is below <expression> with the pushing thrust in the PUSH statement at the specified value.

The setting of <expression> can be specified as follows.

0: A pushing operation is detected if the pushing thrust reaches the specified value with the threshold setting invalid.

1 to 100: The movement speed in the PUSH statement is 100% to specify thresholds with a rate.

#### SAMPLE

PSHJGSP (1) = 50····· Changes the pushing detection speed threshold parameter of axis 1 of robot 1 to 50%.

### **Functions**

#### **Format**

PSHJGSP [<robot number>] (<axis number>)

(Values)

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the value of the pushing detection speed threshold parameter of the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

#### SAMPLE

A=PSHJGSP (1) ..... The pushing detection speed threshold parameter of axis 1 of robot 1 is assigned to variable A.

Specifies/acquires a pushing type parameter.

#### **Format**

- 1. PSHMTD [<robot number>] <expression>
- 2. PSHMTD [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>.....0: Totalizing method, 1: Resetting method

Explanation Changes the pushing type parameter of the robot axis specified by the <robot number> to the value of the <value>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

The pushing type in the PUSH statement can be specified as follows by the <value>.

0: The time for the pushing thrust to reach the specified value is totalized to execute the pushing control end detection.

1: The pushing control end detection is executed only when the pushing thrust continuously reaches the specified value. If the pushing thrust is lower than the specified value, the elapsed time is reset to 0.

In format 1, the change occurs at all axes.

In format 2, the change occurs at the parameter of the axis specified by the <axis number>.

#### SAMPLE

PSHMTD (1) = 1 ············ Changes the pushing type parameter of axis 1 of robot 1 to the resetting type.

#### **Functions**

#### **Format**

PSHMTD [<robot number>] (<axis number>)

Values <robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the value of pushing type parameter of the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

# SAMPLE

A=PSHMTD (1) ..... The pushing type parameter of axis 1 of robot 1 is assigned to variable A.

# **PSHRSLT**

Acquires the status when PUSH statement ends.

#### **Format**

PSHRSLT [<robot number>] <axis number>

Values <robot number>......1 to 4

<axis number>......1 to 6

Explanation Acquires the status at the completion of a "PUSH statement" that was executed for the axis specified by the <axis number> of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> 0 ......The PUSH statement was ended by for a reason other than the arrival of the pushing time.

1 ......The PUSH statement was ended by the arrival of the pushing time

#### SAMPLE

PUSH(3,P1) ..... Moves the axis 3 of robot 1 is under the pushing control to the position specified with P1.

IF PSHRSLT(3) = 1 THEN ····· Ended by the arrival of the pushing time

GOTO \*OK

ELSE ..... Ended for a reason other than the arrival of the pushing time

GOTO \*NG

ENDIF

Specifies/acquires the pushing movement speed parameter.

#### **Format**

- 1. PSHSPD [<robot number>] <expression>
- 2. PSHSPD [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <Pushing speed>......0: Invalid, 1 to 100 (units: %)

Explanation Changes the pushing movement speed parameter of the robot axis specified by the <robot number> to the value indicated in the <expression>. <robot number> can be omitted. If it is omitted, robot 1 is specified.

The motion speed in the PUSH statement is as follows.

- When there is no specification of the S or DS option in the PUSH statement: Maximum speed of a robot (mm/sec. or deg./sec.) x Pushing movement speed (%) x Automatic movement speed (%)
- When there is a specification of the S option in the PUSH statement: Maximum speed of a robot (mm/sec. or deg./sec.) x Pushing movement speed (%) x Automatic movement speed (%) x Program movement speed (%)
- When there is a specification of the DS option in the PUSH statement: Maximum speed of a robot (mm/sec. or deg./sec.) x Pushing movement speed (%) x Movement speed of an axis (%)

#### SAMPLE

PSHSPD (1) = 50 ····· Changes the pushing movement speed parameter of axis 1 of robot 1 to 50%.

# **Functions**

#### **Format**

PSHSPD [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the value of the pushing movement speed parameter of the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

#### SAMPLE

A=PSHSPD (1) ..... The pushing movement speed parameter of axis 1 of robot 1 is assigned to variable A.

#### **Format**

**PSHTIME** 

- 1. PSHTIME [<robot number>] <expression>
- 2. PSHTIME [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......1 to 32767 (unit: ms)

Explanation Changes the pushing time parameter of the robot axis specified by the <robot number> to the value indicated in the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> If the TIM option is omitted in the PUSH statement, the pushing control is executed with the setting of the pushing time parameter.

In format 1, the change occurs at all axes.

In format 2, the change occurs at the axis specified by the <axis number>.

#### SAMPLE

PSHTIME (1) = 1000 ······ Changes the pushing parameter of axis 1 of robot 1 to 1000ms

#### Functions

#### **Format**

PSHTIME [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number>.....1 to 6

Explanation Acquires the value of pushing time parameter of the axis specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

#### SAMPLE

A=PSHTIME (1) ..... The pushing time parameter of axis 1 of robot 1 is assigned to variable A.

Executes a pushing operation for specified axes.

#### **Format**

PUSH[<robot number>](<axis number>, <expression>)[, option]

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......Motor position (mm, degree, pulse) or point expression

Explanation An absolute position movement of the robot axis specified by the <robot number> is executed while the pushing thrust in the direction of forwarding in the axis unit is controlled. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

- Movement type: Pushing PTP movement of specified axis
- Point data setting: Direct coordinate data input, point definition.
- Options : Pushing thrust setting, pushing time, pushing speed setting, STOPON setting

# **Movement type**

#### PTP (point-to-point) of specified axis

PTP movement begins after the operation of the axis specified by the <axis number> is completed (within the tolerance range), controlling the pushing thrust in the forwarding direction of the axis.

The conditions to start the pushing control are as follows.

- Immediately after the start of movement of an axis by the PUSH statement
- After the merge operation is completed (when the PUSH statement is specified in the line next to the movement command with CONT specified)

The conditions to terminate the command are as follows.

- The axis arrives within the tolerance range of the target position.
- The status where the pushing thrust of the axis reaches <pushing thrust value> elapses the time specified to <pushing time value>.

The end status for the PUSH statement can be confirmed with the PSHRSLT statement.

The conditions to cancel the pushing thrust are as follows.

- When a movement command is executed after the PUSH command including STOP is finished
- When a servo off occurs
- When the power source to the controller is interrupted and restarted

N

0

P

Q

R

5

V

W

X

Y

Z

If the next command following to the PUSH statement is an executable command such as a signal output command, the next command will start when the pushing conditions of an axis to be moved are satisfied, or when an axis arrives within the tolerance range of the target position. Example:

Signal output (DO, etc.)	Signal is output when the pushing conditions are satisfied or within the tolerance range.
DELAY	DELAY command is executed and standby starts, when the pushing conditions are satisfied or within the tolerance range.
HALT	Program stops and is reset when axis enters the OUT position range. Therefore, axis movement also stops.
HALTALL	When the pushing conditions are satisfied or within the tolerance range, the programs in execution are all stopped, task 1 is reset, and other tasks are terminated. Therefore, axis movement also stops.
HOLD	Program temporarily stops when axis enters the OUT position range. Therefore, axis movement also stops.
HOLDALL	When the pushing conditions are satisfied or within the tolerance range, the programs in execution are all temporarily stopped. Therefore, axis movement also stops.
WAIT	WAIT command is executed, when the pushing conditions are satisfied or within the tolerance range.

SAMPLE
PUSH(1,P0) ····· Axis 1 moves from its current position
to the position specified by PO.

# Point data setting types

# Direct numeric value input

The motor position is specified directly in <expression>.

If the motor position's numeric value is an integer, this is interpreted as a "pulse" unit. If the motor position's numeric value is a real number, this is interpreted as a "mm/degrees" unit, and each axis will move from the 0-pulse position to a pulse-converted position.

SAMPLE
PUSH(1,10000) ······ Axis 1 of robot 1 moves from its current
position to the 100000 pulse position.
PUSH[2](2,90.00) Axis 2 of robot 2 moves from its
current position to the 90° position
(when axis 2 is a rotating axis.)

#### Point definition

Point data is specified in <expressions>. The axis data specified by the <axis number> is used. If the point expression is in "mm/degrees" units, movement for each axis occurs from the 0-pulse position to the pulse-converted position.

SAMPLE
PUSH(1,P1) ····· Axis 1 of robot 1 moves from its current
position to the position specified by P1.
PUSH[2](2,P90) ······ Axis 2 of robot 2 moves from its
current position to the position
specified by P90 (deg.) (when
axis 2 is a rotating axis.)

## **Option types**

## Pushing thrust setting

#### **Format**

F=<expression>

Values <expression>.....-1000 to 1000 (units: %)

**Explanation** 

The pushing thrust in the forwarding direction of an axis is specified as an <expression>.

The actual pushing thrust is determined as shown below.

• Rated thrust x <expression>/100

If <pushing thrust value> is omitted, <pushing thrust value> specified with the parameter is used.

#### SAMPLE

PUSH(1,10000), F=10 ······ Axis 1 of robot 1 moves from its current position to the 100000 pulse position with the pushing thrust at 10% of the rated thrust.

## Pushing time setting

## **Format**

TIM=<expression>

Values <expression>......1 to 32767 (units: ms)

**Explanation** 

The time to keep pushing with the specified pushing thrust is specified as an <expression>.

When the status where the pushing thrust reaches the specified value exceeds <expression>, the PUSH statement terminates.

If this option is omitted, the setting of the parameter is used.

### SAMPLE

PUSH(1,10000),S=10 ······ Axis 1 moves from its current position to the 100000 pulse position with the speed at 10% of the multiplication of the pushing movement speed and the automatic movement speed.

**PUSH** 

## Speed setting

### **Format**

- 1. SPEED=<expression>
- 2. S=<expression>

**Values** 

<expression>......1 to 100 (units: %)

### **Explanation**

The program movement speed is specified in <expression>.

The actual speed is determined as shown below.

• Robot's max. speed (mm/sec, or deg/sec) x pushing movement speed (%) x automatic movement speed (%) x program movement speed (%)

This option is enabled only for the specified PUSH statement.

### SAMPLE

PUSH(1,10000), S=10 ······· Axis 1 moves from its current position to the 100000 pulse position with the speed at 10% of the multiplication of the pushing movement speed and the automatic movement speed.

#### **Format**

- DSPEED=<expression>
- 2. DS=<expression>

#### **Explanation**

The axis movement speed is specified in <expression>.

The actual speed is determined as shown below.

• Robot's max. speed (mm/sec, or deg/sec) x pushing movement speed (%) x movement speed of an axis (%)

This option is enabled only for the specified PUSH statement.

• Movement always occurs at the DSPEED <expression> value (%) without being affected by the automatic movement speed value (%).

### SAMPLE

PUSH(1,10000),DS=0.1 ····· Axis 1 moves from its current position to the 100000 pulse position with the speed at 0.1% of the pushing movement speed.

## STOPON conditions setting

#### **Format**

STOPON <conditional expression>

### **Explanation**

Stops movement when the conditions specified by the conditional expression are met. Because this is a deceleration type stop, there will be some movement (during deceleration) after the conditions are met.

If the conditions are already met before movement begins, no movement occurs, and the command is terminated.

This option is enabled only by program execution.

## SAMPLE



• When the conditional expression used to designate the STOPON conditions is a numeric expression, an expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

Related commands

PSHFRC, PSHTIME, PSHMTD, PSHDSP, PSHSPD, PSHRSLT, CURTRQ, CURTQST

N

O

r

K

**3** 

U

V

W

Χ

Y

# RADDEG

Performs a unit conversion (radians → degrees)

## **Format**

RADDEG(<expression>)

Values

<expression>.....Angle (units: radians)

**Explanation** Converts the <expression> value to degrees.

### SAMPLE

LOCR(P0) = RADDEG(ATN(B)) ··· Converts the variable B arctangent value to degrees, and assigns it to R-data of

Related commands

ATN, COS, DEGRAD, SIN, TAN

- 1. REM <character string>
- 2. ' <character string>

Explanation All characters which follow REM or an apostrophe (') are handled as a comment. This comment statement is used only to insert comments in the program, and it does not execute any command. The apostrophe (1) can be entered at any point in the line.

## SAMPLE

REM \*\*\* MAIN PROGRAM \*\*\* \*\*\* SUBROUTINE \*\*\* HALT ' HALT COMMAND

0

85

# RESET

Turns OFF the bits of specified ports, or clears variables

 $DOm([b, \cdot \cdot \cdot, b])$  $DO(mb, \cdot \cdot \cdot, mb)$  $MOm([b, \cdot \cdot \cdot, b])$  $MO(mb, \cdot \cdot \cdot, mb)$  $TOn([b, \cdot \cdot \cdot, b])$  $TO(n-b, \cdot \cdot \cdot, nb)$  $LOn([b, \cdot \cdot \cdot, b])$  $LO(nb, \cdot \cdot \cdot, nb)$  $SOm([b, \cdot \cdot \cdot, b])$  $SO(mb, \dots, mb)$ 

Format 1 RESET

CAUTION

Output to ports "0" and "1"

is not allowed at DO, and

• For details regarding bit definitions, see Chapter 3

"10 Bit Settings".

SO.

REFERENCE

Format 2

## RESET TCOUNTER

**Values** 

```
m: port number......2 to 7, 10 to 17, 20 to 27
n: port number ......0, 1
b: bit definition ......0 to 7
```

**Explanation** Format 1: Turns the bits of specified ports OFF.

Format 2: Clears the 10ms counter variables (10ms counter variables are used to measure the time in 10ms units).

If multiple bits are specified, they are expressed from the left in descending order (large to small).

If the [b,...,b] data is omitted, all 8 bits are processed.

# SAMPLE RESET DO2() ······ Turns OFF DO(27 to 20). RESET DO2(6,5,1) ..... Turns OFF DO(26, 25, 21). RESET (37,35,27,20) ..... Turns OFF DO(37, 35, 27, 20). RESET TCOUNTER......Clears the 10ms counter variables.

Related commands

SET, DO, MO, SO, TO, LO

Restarts another task during a temporary stop

Explanation Restarts another task that has been temporarily stopped (SUSPEND status).

A task can be specified by the name or the number of a program in execution.

**Ø** MEMO

• If a task (program) not temporarily stopped is specified and executed, an error occurs.

```
SAMPLE
START <SUB PGM>, T2
   FLAG=1
*L0:
   IF FLAG=1 AND DI2(0)=1 THEN
      SUSPEND T2
      FLAG=2
   WAIT DI2(0)=0
   ENDIF
   IF FLAG=2 AND DI2(0)=1 THEN
      RESTART T2
      FLAG=1
      WAIT DI2(1)=0
   ENDIF
   MOVE P, P0
   MOVE P, P1
   GOTO *L0
   HALTALL
Program name: SUB PGM
*SUBPGM:
' SUBTASK ROUTINE
*SUBTASK:
   DO2(0)=1
   DELAY 1000
   DO2(0) = 0
   DELAY 1000
   GOTO *SUBPGM
   EXIT TASK
```

Related commands

CUT, EXIT TASK, START, SUSPEND

Reference

For details, refer to the "Multi-Task" item.

RESTART • 7-145

Ν

0

P

Q

R

S

V

W

X

Y

7

## RESUME

Resumes program execution after error recovery processing

## **Format**

- 1. RESUME NEXT
- 2. RESUME < label>

• For details, see "62 ON ERROR GOTO".

**Explanation** Resumes program execution after recovery from an error.

Depending on its location, a program can be resumed in the following 3 ways:

1. RESUME The program resumes from the command which caused the

2. RESUME NEXT The program resumes from the next command after the

command which caused the error.

3. RESUME < label> The program resumes from the command specified by the

<label>.



- The RESUME statement can also be executed in an error processing routine.
- "Error recovery processing is not possible for serious errors such as "17.4 : Overload", etc.

Related commands

ON ERROR GOTO

Q

```
Format
GOSUB < label>
                                   * GOSUB can also be expressed as "GO SUB".
<label>:
   :
RETURN
```

Explanation Ends the subroutine and returns to the next line after the jump source GOSUB

All subroutines (jump destinations) specified by a GOSUB statement must end with a RETURN statement. Using the GOTO statement, etc., to jump from a subroutine will cause an error such as the "5.12: Stack overflow", etc.

```
SAMPLE
*ST:
   MOVE P, P0
   GOSUB *CLOSEHAND
   MOVE P, P1
   GOSUB *OPENHAND
GOTO *ST
HALT
' SUB ROUTINE
*CLOSEHAND:
   DO(20) = 1
RETURN
*OPENHAND:
   DO(20) = 0
RETURN
```

Related commands

**GOSUB** 

RIGHT\$(<character string expression>,<expression>)

Values <expression>......0 to 75

Explanation This function extracts a character string with the digits specified by the <expression> from the right end of the character string specified by <character string expression>.

The <expression> value must be between 0 and 75, otherwise an error will occur. If the <expression> value is 0, then RIGHT\$ will be a null string (empty character string).

If the <expression> value has more characters than the <character string expression>, RIGHT\$ will become the same as the <character string expression>.

## SAMPLE

B\$=RIGHT\$(A\$,4) ..... 4 characters from the right end of A\$ are assigned to B\$.

Related commands LEFT\$, MID\$

P

Q

R

S

T

U

V

W

Χ

Y

RIGHTY [<robot number>]

Values

<robot number>......1 to 4

Explanation This statement specifies the robot with <robot number> by the right-handed movement to a point specified in the Cartesian coordinate. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> This statement only selects the hand system, and does not move the robot. If executed while the robot arm is moving, execution waits until movement is complete (positioned within tolerance range).

> > ......Specifies a Robot 1 "left-

This command is only valid for SCARA robots.


## SAMPLE

...... Specifies a Robot 1 "right-RIGHTY handed system" setting.(see Fig.1 below). MOVE P, P1

handed system" setting.(see Fig.2 below).

MOVE P, P1 RIGHTY HALT

# SAMPLE:LEFTY/RIGHTY



33818-R7-00

Related commands

**LEFTY** 

RSHIFT(<expression 1>,<expression 2>)

Explanation Shifts the <expression 1> bit value to the right by the amount of <expression 2>. Spaces left blank by the shift are filled with zeros (0).

## SAMPLE

A=RSHIFT(&B10111011,2) ..... The 2-bit-right-shifted &B10111011 value (&B00101110) is assigned to A.

Related commands

LSHIFT

П

J

W

Χ

Y

L

# SELECT CASE to END SELECT

Executes the specified command block in accordance with the <expression> value

```
Format
SELECT [CASE] <expression>
   CASE <expression list 1>
      [command block 1]
   [CASE <expression list 2>
      [command block 2]]
   [CASE ELSE
      [command block n]]
END SELECT
```

Explanation These statements execute multiple command blocks in accordance with the <expression> value. The setting method is as follows.

- 1. The <expression list> following CASE statement comprises multiple numerical expressions and character expressions separated from each other by a comma ( , ).
- 2. If the <expression> value matches one of expressions contained in the <expression list>, the specified command block is executed. After executing the command block, the program jumps to the next command which follows the END SELECT statement.
- 3. If the <expression> value does not match any of the expressions contained in the <expression list>, the command block indicated after the CASE ELSE statement is executed. After executing the command block, the program jumps to the next command which follows the END SELECT statement.
- 4. If the <expression> value does not match any of the expressions contained in <expression list> and no CASE ELSE statement exists, the program jumps to the next command following the END SELECT statement.

```
SAMPLE
WHILE -1
SELECT CASE DI3()
   CASE 1,2,3
      CALL *EXEC(1,10)
   CASE 4,5,6,7,8,9,10
      CALL *EXEC(11,20)
   CASE ELSE
      CALL *EXEC(21,30)
END SELECT
WEND
HALT
```

Examples of erroneous

writing to a read-only file:

• Examples of data format

SEND CMU TO DIR

SEND PGM TO PNT

SEND SI() TO SFT

SEND PNT TO SIO

mismatches:

SEND

## **Format**

SEND <read file> TO <write file>

Explanation Sends < read file > data to the < write file >.

An entire DO, MO, TO, LO, SO, or SOW port (DO(), MO(), etc.), cannot be specified as a write file.

Moreover, some individual files (DOn(), MOn(), etc.) cannot be specified as a write file. For details, refer to Chapter 8 "Data file description".

Writing to read-only files (indicated by a "x" in the "WRITE" column of the table shown below) is not permitted.

Even if the READ and WRITE files are specified correctly, it may not be possible to execute them if there is a data format mismatch between the files.

Туре	File Name	Definition Format		READ	MOITE
		All	Individual File	READ	WRITE
User	All files	ALL		0	0
	Program	PGM	<bbbbbbbb></bbbbbbbb>	0	0
	Point	PNT	Pn	0	0
	Point comment	PCM	PCn	0	0
	Parameter	PRM	/ccccc/	0	0
	Shift definition	SFT	Sn	0	0
	Hand definition	HND	Hn	0	0
	Pallet definition	PLT	PLn	0	0
Variable,	Variable	VAR	abby	0	0
Constant	Array variable	ARY	abby(x)	0	0
	Constant		"ccc"	0	×
Status	Program directory	DIR	< <bbbbbbbb>&gt;</bbbbbbbb>	0	×
	Parameter directory	DPM		0	×
	Machine reference	MRF		0	×
	Error log	LOG		0	×
	Remaining memory size	MEM		0	×
Device	DI port	DI()	Dln()	0	×
	DO port	DO()	DOn()	0	0
	MO port	MO()	MOn()	0	0
	TO port	TO()	TOn()	0	0
	LO port	LO()	LOn()	0	0
	SI port	SI()	SIn()	0	×
	SO port	SO()	SOn()	0	0
	SIW port	SIW()	SIWn()	0	×
	SOW port	SOW()	SOWn()	0	0
	RS-232C	CMU		0	0
	Ethernet	ETH		0	0
Other	File END code	EOF		0	×

N: Number

a: Alphabetic character

b: Alphanumeric character or underscore ( )

: Permitted

c: Alphanumeric character or special symbol

x: Expression (array argument) y: Variable type

 $\times\,$ : Not permitted



- The following cautions apply when a restart is performed after a stop occurred during execution of the SEND statement:
  - 1. When reading from RS-232C / Ethernet (SEND CMU TO XXX, SEND ETH TO XXX): When the SEND statement is stopped during data reading from the reception buffer, the data acquired up to that point is discarded.
  - 2. When writing to RS-232C / Ethernet (SEND XXX TO CMU, SEND XXX TO ETH): When the SEND statement is stopped during data writing to the transmission buffer, the data is written from the beginning.

SAMPLE				
SEND PGM TO CMU······Outputs all user programs from the RS-232C port.				
SEND < PRG1 > TO CMU ········· Outputs the PRG1 program from the RS-232C port.				
SEND CMU TO PNT······ Inputs a point data file from the RS-232C port.				
SEND "T1" TO CMU Outputs the "T1" character string from the RS-232C port.				
SEND CMU TO A\$ Inputs character string data to variable A\$ from the RS-232C port.				

Reference For details, refer to Chapter 8 "Data file description".

N

0

P

Q

R

S

V

X

Y

**CAUTION** 

• Keep out of the robot

movement range while the motor power is turned OFF by the SERVO OFF

statement. Always check

that the Emergency Stop is ON when working within

the robot movement

area.

**SERVO** 

ON OFF FREE PWR	[( <axis number="">)]</axis>
	OFF FREE

Values <robot number>......1 to 4 <axis number>......1 to 6

**Explanation** This statement controls the servo ON/OFF at the specified axes or all axes. When the <axis number> is specified, only the specified axis becomes an object. When not specified, all axes become an object.

- ON .....Turns the servo ON.
- OFF......Turns the servo OFF and applies the dynamic brake. Axes equipped with brakes are all locked by the brake.
- FREE.....Turns the servo OFF and releases the dynamic brake. The brakes are released at all axes with brakes.
- • This statement is executed after the operation of all axes of the specified robot has been complete (after positioned within the tolerance).

SAMPLE
SERVO ON
brake.  SERVO FREE(3) The axis 3 (Z-axis) servo is turned OFF, and the brake is released.

Turns the bit at the specified output port ON

**Format** SET

[, <time>]

 $DOm([b, \cdot \cdot \cdot, b])$ DO  $(mb, \cdot \cdot \cdot, mb)$  $MOm([b, \cdot \cdot \cdot, b])$  $MO (mb, \cdot \cdot \cdot , mb)$ 

 $TOn([b, \cdot \cdot \cdot, b])$ TO  $(nb, \dots, nb)$ 

 $LOn([b, \cdot \cdot \cdot, b])$ LO  $(nb, \dots, nb)$ 

 $SOm([b, \cdot \cdot \cdot, b])$ SO  $(mb, \dots, mb)$ 

Values

m: port number ......2 to 7, 10 to 17, 20 to 27 n: port number......0, 1

b: bit definition ...... 0 to 7

<time>......10 to 3600000 (units: ms)

CAUTION

• Output to ports "0" and "1" are not allowed at DO, and SO.



• For bit setting details, see Chapter 3 "10 Bit Settings".

**Explanation** Turns ON the bits of specified ports.

The pulse output time (unit: ms) is specified by the <time> value. When the specified time elapses, the output is turned OFF, and command execution ends.

If multiple bits are specified, they are expressed from the left in descending order (large to small).

If the [b,...,b] data is omitted, all 8 bits are processed.

If no hardware port exists, nothing is output.

SAMPLE

SET DO2() ..... Turns ON DO(27 to 20). SET DO2(6,5,1),200 ..... DO(26,25,21) switches ON for

200ms.

SET DO(37,35,27,20) ...... Turns DO(37, 35, 27, 20) ON.

Related commands

RESET, DO, MO, SO, TO, LO

# SHARED

Enables sub-procedure referencing without passing on the variable

### **Format**

<variable>[()][,<variable>[()]...]

The program level code is a program written outside the sub-procedure.

SAMPLE

Explanation This statement allows variables declared with a program level code to be referenced with a sub-procedure without passing on the variables as dummy arguments.

The program level variable used by the sub-procedure is specified by the <variable>

A simple variable or an array variable followed by parentheses is specified. If an array is specified, that entire array is selected.



- Normally, a <dummy argument> passes along the variable to a sub-procedure, but the SHARED statement allows referencing to occur without passing along the variable.
- The SHARED statement allows variables to be shared only between a program level code and sub-procedure which are within the same program level.

## DIM Y! (10) X!=2.5Y!(10)=1.2CALL \*DISTANCE CALL \*AREA HALT SUB \*DISTANCE SHARED X!, Y!() ...... Variable referencing declared by SHARED. PRINT X!^2+Y!(10)^2····· The variable is shared. END SUB SUB \*AREA DIM Y! (10)

PRINT X!\*Y! (10) ..... The variable is not shared.

Related commands

END SUB

SUB, END SUB

Z

Values <robot number>......1 to 4

Explanation Sets the shift coordinates in accordance with the shift data specified by the <shift variable> to the robot specified by the <robot number>.

**MEMO** 

• This statement is executed after axis positioning is complete (within the tolerance range).

#### SAMPLE

SHIFT S1 MOVE P,P10 SHIFT S[A] MOVE P,P20 HALT

Related commands Shift definition statement, shift assignment statement

SIN

## **Format**

SIN(<expression>)

Values

<expression>......Angle (units: radians)

**Explanation** This function gives the sine value for the <expression> value.

### SAMPLE

A(0)=SIN(B\*2+C) ....... Assigns the expression B\*2+C sine value to array A(0). A(1)=SIN(DEGRAD(30)) ...... Assigns a 30.0° sine value to

array A (1).

Related commands ATN, COS, DEGRAD, RADDEG, TAN

0

۲

Q

R

5

V

W

X

Y

Defines the shift coordinates in the program

**Format** 

Sn = x y z r

Values

n ......0 to 39

x, y, z, r.....-99,999.99 to 99,999.99

- All input values are handled as constants.
- If the controller power is turned off during execution of a shift coordinate definition statement, a memoryrelated error such as "9.6: Shift check-sum error" may occur.

Explanation Defines shift coordinate values in order to shift the coordinates for robot movement. Only "mm" units can be used for these coordinate values ("pulse" units cannot be used).

- 1. "n" indicates the shift number.
- 2. The "x" to "r" input data must be separated with spaces (blanks).
- 3. The "x" to "r" input data is recognized as "mm" unit data.
- 4. "x" to "z" correspond to the Cartesian coordinate system's x, y, z coordinate shift values, and "r" corresponds to the xy coordinates' rotational shift values.

SAMPLE S0 = 0.00 100.00 S1 =

0.00 0.00 0.00 200.00 50.00 90.00

P3 = 100.00 0.00 0.00 0.00 0.00 0.00

SHIFT SO

MOVE P, P3

SHIFT S1

MOVE P, P3

HALT

Related commands

Shift assignment statement, SHIFT

Sn 7-159

SO

Outputs a specified value to the serial port

## **Format**

- 1. [LET]  $SOm([b, \cdot \cdot \cdot , b]) = \langle expression \rangle$
- 2. [LET] SO  $(mb, \dots, mb) = \langle expression \rangle$

Values

m: port number......2 to 7, 10 to 17, 20 to 27 b: bit definition .......0 to 7

Explanation Outputs a specified value to the SO port.

Only the <value> data's integer-converted lower bits corresponding to the bits defined at the left side can be output.

If multiple bits are specified, they are expressed from the left in descending order (large to small).

If the [b,...,b] data is omitted, all 8 bits are processed.

If no hardware port exists, nothing is output.

• Outputs to SOO() and SO1() are not possible.

**CAUTION** 



• For bit setting details, see Chapter 3 "10 Bit Settings".

## SAMPLE

SO3()=15 .....SO (33, 32, 31, 30) are turned ON, and SO (37, 36, 35, 34) are turned OFF.

SO(37,35,27,20)=A------ The lower 4 bits of integer-converted variable A are

output to SO (37, 35, 27, 20).

Related commands

RESET, SET

Changes the program movement speed

#### **Format**

SPEED [<robot number>] <expression>

Values

<robot number>......1 to 4

<expression>......1 to 100 (units: %)

 Automatic movement speed

Specified by programming box operation or by the ASPEED command.

• Program movement speed

Specified by SPEED commands or MOVE, DRIVE speed options.

Explanation Changes the program movement speed value of the robot specified by the <robot number> to the speed indicated by the <expression>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> This speed change applies to all the robot axes and auxiliary axes of the specified robot.

> The operation speed is determined by multiplying the automatic movement speed (specified from the programming box and by the ASPEED command), by the program movement speed (specified by SPEED command, etc.).

Operation speed = automatic movement speed x program movement speed.

Example:

Automatic movement speed ... 80%

Program movement speed ... 50%

Movement speed =  $40\% (80\% \times 50\%)$ 

**Functions** 

**Format** 

SPEED [<robot number>]

Values

<robot number>......1 to 4

Explanation Acquires the program movement speed value of a robot specified by the <robot

The <robot number> can be omitted. When the <robot number> is omitted, the robot 1 is specified.

SAMPLE

ASPEED 100

SPEED 70

MOVE P,P0 ...... Moves from current position to P0 at a speed of 70% (=100 \* 70).

SPEED 50

MOVE P, P1 ..... Moves from current position to P1 at a speed of 50% (=100 \* 50).

MOVE P, P2, S=10 ····· Moves from current position to P2 at a speed of 10% (=100 \* 10).

HALT

Related commands

**ASPEED** 

Q

SQR(<expression>)

Values <expression>......0 or positive number.

**Explanation** Gives the square root of the <expression> value. An error occurs if the <expression> value is a negative number.

## SAMPLE

 $A=SQR(X^2+Y^2)\cdots$  The square root of  $X^2+Y^2$  is assigned to variable A.

N

0

P

Q

R

S

Τ

U

V

W

Χ

Y

## START Starts a new task

Format	
START	"< " <pre>"&lt; "<pre>program name</pre>" &gt;"  [,Tn [, p]] PGm</pre>

Values m: Program number ...... 0 to 99 n: Task number ...... 1 to 16 p: Task priority ranking ......1 to 64

Explanation Starts task "n" specified by the program with the "p" priority ranking.

If task number "n" is omitted, the task with the smallest number among the tasks yet to be started is automatically specified.

If a priority ranking is not specified, "32" is adopted as the priority ranking for this task.

The smaller the priority number, the higher the priority (high priority:  $1 \leftrightarrow low$ priority: 64).

When a RUNNING status occurs at a task with higher priority, all tasks with lower priority also remain in a READY status.

```
SAMPLE
```

```
START <SUB PGM>, T2, 33
   MOVE P, P0, P1
GOTO *ST
HALT
Program name:SUB_PGM
*SUBPGM:
'SUBTASK ROUTINE
*SUBTASK:
   P100 = WHERE
   IF LOCZ(P100) > 10000 THEN
      DO(20) = 1
   ELSE
      DO(20) = 0
   ENDIF
GOTO *SUBPGM
EXIT TASK
```

Related commands

CUT, EXIT TASK, RESTART, SUSPEND, CHGPRI

Q

STR\$(<expression>)

**Explanation** Converts the value specified by the <expression> to a character string. The <expression> specifies an integer or real number value.

### SAMPLE

B\$=STR\$(10.01)

Related commands

VAL

0

P

Q

R

5

T

V

W

X

Υ

\_

## SUB to END SUB

Defines a sub-procedure

### **Format**

```
SUB <label> [(<dummy argument> [, <dummy argument> ...])]
   <command block>
END SUB
```

**Explanation** Defines a sub-procedure.

The sub-procedure can be executed by a CALL statement. When the END SUB statement is executed, the program jumps to the next command after the CALL statement that was called. Definitions are as follows.

- 1. All variables declared within the sub-procedure are local variables, and these are valid only within the sub-procedure. Local variables are initialized each time the sub-procedure is called up.
- 2. Use a SHARED statement in order to use global variables (program level).
- 3. Use a <dummy argument> when variables are to be passed on. If two or more dummy arguments are used, separate them by a comma (,).
- 4. A valid <dummy argument> consists of a name of variable and an entire array (array name followed by parentheses). An error will occur if array elements (a <subscript> following the array name) are specified.



- Sub-procedures cannot be defined within a sub-procedure.
- A label can be defined within a sub-procedure, but it cannot jump (by a GOTO or GOSUB statement) to a label outside the sub-procedure.
- Local variables cannot be used with PRINT and SEND statements.

```
SAMPLE 1
```

```
A=1
CALL *TEST
PRINT A
HALT
' SUB ROUTINE: TEST
SUB *TEST
  A = 50
        ······Handled as
                                      а
                                         different
                        variable than the "A" shown
                        above.
END SUB
```

• In the above example, the program level variable "A" is unrelated to the variable "A" within the sub-procedure. Therefore, the value indicated in the 3rd line PRINT statement becomes "1".

P

Q

R

S

Ш

W

7

```
SAMPLE 2
X% = 4
Y\% = 5
CALL *COMPARE( REF X%, REF Y%)
PRINT X%,Y%
Z% = 7
₩% = 2
CALL *COMPARE( REF Z%, REF W% )
PRINT Z%, W%
HALT
' SUB ROUTINE: COMPARE
SUB *COMPARE( A%, B%)
   IF A% < B% THEN
      TEMP% = A%
      A% = B%
     B% = TEMP%
   ENDIF
END SUB
```



• In the above example, different variables are passed along as arguments to call the subprocedure 2 times.

Related commands

CALL, EXIT SUB, SHARED

Temporarily stops another task which is being executed

**Format** SUSPEND | Tn "< "<pre>"< name</pre>" >" PGm

Values

m: Program number .....0 to 99 n: Task number ......1 to 16

Explanation Temporarily stops (suspends) another task which is being executed. A task can be specified by the name or the number of a program in execution.

> This statement can also be used for tasks with a higher priority ranking than this task itself.

MEMO

• If a task (program) not active is specified for the execution, an error occurs.

SAMPLE

SUSFLG=0 \*L0: MOVE P, P0 MOVE P, P1 WAIT SUSFLG=1 SUSPEND T2 SUSFLG=0 GOTO \*L0 HALT Program name: SUB PGM \*SUBPGM: ' SUBTASK ROUTINE \*SUBTASK: WAIT SUSFLG=0 DO2(0)=1DELAY 1000 DO2(0) = 0

START <SUB PGM>,T2

Related commands

DELAY 1000 SUSFLG=1 GOTO \*SUBPGM EXIT TASK

CUT, EXIT TASK, RESTART, SUSPEND

Q

SWI "<"<pre>rogram name>">"

Explanation This statement switches from the current program to the specified program, starting from the first line.

> Although the output variable status is not changed when the program is switched, the dynamic variables and array variables are cleared. The program name to be switched to must be enclosed in angular brackets (< >).



**SWI** 

• If the program specified as the switching target does not exist, a "3.3: Program doesn't exist" (code: &H0303) error occurs and operation stops.

## SAMPLE

SWI <ABC> ..... Switches the execution program to "ABC".

Acquires the tangent value for a specified value

## **Format**

TAN(<expression>)

Values

<expression>......Angle (units: radians)

**Explanation** Gives a tangent value for the <expression> value. An error will occur if the <expression> value is a negative number.

SAMPLE

A(0)=B-TAN(C) ...... The difference between the tangent values of variable B and variable C is assigned to array A(0).

A(1)=TAN(DEGRAD(20))  $\cdots$  The 20.0 ° tangent value is assigned to array A (1).

Related commands

ATN, COS, DEGRAD, RADDEG, SIN

Ν

 $\overline{\phantom{a}}$ 

P

Q

R

c

Т

Α,,

X \_\_\_\_

Ш

# **TCOUNTER**

Timer & counter

## **Format**

#### TCOUNTER

Explanation Outputs count-up values at 1ms intervals starting from the point when the TCOUNTER variable is reset.

After counting up to 65,535, the count is reset to 0.

#### SAMPLE

MOVE P, P0

WAIT ARM

RESET TCOUNTER

MOVE P, P1

WAIT ARM

A = TCOUNTER

PRINT TCOUNTER ..... Displays the P0 to P1 movement time at the programming box until movement enters the tolerance range.

Related commands

RESET



Acquires the current time

## Format

TIME\$

Explanation Acquires the current time in an hh:mm:ss format character string. "hh" is the hour, "mm" is the minutes, and "ss" is the seconds. The clock can be set in the SYSTEM mode's initial processing.

SAMPLE

A\$=TIME\$ PRINT TIME\$

Related commands

DATE\$, TIMER

# **TIMER**

Acquires the current time



# CAUTION

 The time indicated by the internal clock may differ somewhat from the actual time.

## **Format**

TIMER

**Functions** Acquires the current time in seconds, counting from 12:00 midnight. This function is used to measure a program's run time, etc.

The clock can be set in the SYSTEM mode's initial processing.

## SAMPLE

A%=TIMER

FOR B=1 TO 10

MOVE P, P0

MOVE P, P1

NEXT

A%=TIMER-A%

PRINT A%/60;":";A% MOD 60

HALT

Related commands

TIME\$

W

Λ

Y

Outputs a specified value to the TO port

## **Format**

- 1. [LET] TOm( $[b, \cdot \cdot \cdot , b]$ ) = <expression>
- [LET] TO  $(mb, \dots, mb) = \langle expression \rangle$

Values

m: port number......0, 1 b: bit definition ......0 to 7

Explanation Outputs the specified value to the TO port. The output value is the expression's integer-converted lower bits corresponding to the bit definition specified at the left side.

> If multiple bits are specified, they are expressed from the left in descending order (large to small).

If the [b,...,b] data is omitted, all 8 bits are processed.

The OFF/ON settings for bits which are being used in a SEQUENCE program have priority while the SEQUENCE program is running.

## SAMPLE

TOO() = &B00000110

Related commands

RESET, SET

Q

TOLE

- 1. TOLE [<robot number>] <expression>
- 2. TOLE [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......Varies according to the motor which has been specified (unit: pulse)

Explanation Change the tolerance parameter of the robot axis specified by the <robot number> to the <expression> value (unit: pulse). The <robot number> can be omitted. If it is omitted, robot 1 is specified.

Format 1: The change is applied to all axes of the specified robot.

Format 2: The change is applied to only the axis specified by the <axis number> of the specified robot.



- If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error occurs and the command execution is stopped.
- This statement is executed after positioning of the specified axes is complete (within the tolerance range).

## **Functions**

#### **Format**

TOLE (<robot number>)

**Values** 

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the tolerance parameter values for the axis-specified by the <axis number> among the robot axes specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

## SAMPLE

```
' CYCLE WITH DECREASING TOLERANCE
DIM TOLE (5)
FOR A=200 TO 80 STEP -20
   GOSUB *CHANGE TOLE
  MOVE P, P0
  MOVE P, P1
NEXT A
C=TOLE(2) ..... The tolerance parameter of axis 2 of
                           robot 1 is assigned to variable C.
HALT
*CHANGE TOLE:
FOR B=1 TO 4
   TOLE(B) = A
NEXT B
RETURN
```

### TORQUE

Specifies/acquires the maximum torque command value which can be set for a specified axis

### **Format**

TORQUE [<robot number>] (<axis number>) = <expression>

Values

<robot number>......1 to 4 <axis number>......1 to 6 <expression>......1 to 100 (units: %)

### CAUTION

- If the specified torque limit is too small, the axis may not move. In this case, press the emergency stop button before proceeding with the operation.
- If the specified value is less than the rated torque, an error may not occur even if the robot strikes an obstacle.

Explanation Changes the maximum torque command value of the axis specified by the <axis number> of the robot specified by the <robot number> to the value of <expression>. The new value is enabled after the next movement command (MOVE or DRIVE statement, etc.) is executed. The torque parameter value does not change.

The conditions to cancel a torque limit are as follows.

- The TORQUE command for the same axis is executed.
- The controller power turned off and then on again.
- The axis polarity parameter is changed or a parameter is initialized.
- The server is turned off.

The conditions to temporarily change a torque limit are as follows.

- A return- to-origin is in execution.
- The PUSH statement is in execution (only the direction of a movement is changed). The torque limit returns to the specified value when a movement command such as the next MOVE statement is executed.



• If an axis that is set to "no axis" in the system generation is specified, a "5.37: Specification mismatch" error message displays and command execution is stopped.

### **Functions**

### **Format**

TORQUE [<robot number>] (<axis number>)

Values

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Acquires the torque setting value for the axis specified by the <axis number> of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

SAMPLE	
	Changes the max. torque of axis 1 of robot 1 to 50%.
f t	Moves the axis 1 of robot 1 from its current position to the point specified by P1.
	(Change the max. torque at
	the same time with the start
	of the movement.)
	Waits for the completion of an operation of axis 1 of robot 1.
ā	Returns the max. torque of axis 1 of robot 1 to the original value (100%).
·	Moves the robot 1 from its current position to the point specified with P0.
ē	(Returns the max. torque of axis 1 to the original value (100%) at the same time with the start of a movement.)

Related commands

CURTRQ, PUSH

VAL (<character string expression>)

Explanation Converts the numeric value of the character string specified in the <character string expression> into an actual numeric value.

> The value may be expressed in integer format (binary, decimal, hexadecimal), or real number format (decimal point format, exponential format).

> The VAL value becomes "0" if the first character of the character string is "+", "-", "&" or anything other than a numeric character.

> If there are non-numeric characters or spaces elsewhere in the character string, all subsequent characters are ignored by this function.

However, for hexadecimal expressions, A to F are considered numeric characters.

### SAMPLE

A=VAL("&B100001")

WAIT

WAIT <conditional expression> [, <expression>]

Values <expression>......1 to 3600000 (units: ms)

Explanation Establishes a "wait" status until the condition specified by the <conditional expression> is met. Specify the time-out period (unit: ms) in the <expression>.

If a time-out period has been specified, this command terminates if the time-out period elapses before the WAIT condition is met. The minimum wait time is 1ms but changes depending on the execution status of other tasks.

• When the conditional expression is a numeric expression, an expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

SAMPLE WAIT A=10 ..... A wait status continues until variable A becomes 10. WAIT DI2( )=&B01010110 ····· Waits until DI(21),(22),(24),(26) turned on, are DI(20),(23),(25),(27) is turned WAIT DI2(4,3,2)=&B101  $\cdots$  Waits until DI(22) and DI(24) are turned on, and DI(23) is turned off. WAIT DI(31)=1 OR DO(21)=1 $\cdots$ A wait status continues until either DI (31) or DO(21) turns ON. WAIT DI(20)=1,1000 ·········· A wait status continues until DI(20) turns ON. If DI(20) fails to turn ON within 1 second, the command is terminated.

Related commands DRIVE, DRIVEI, MOVE, MOVEI

0

P

Q

R

S

Ш

W

X

Υ

7-178 Chapter 7 Robot Language Lists

Waits until the robot axis operation is completed

For	0.0	
1		rei

WAIT ARM [<robot number>] [(<axis number>)]

Values

<robot number>......1 to 4 <axis number>......1 to 6

Explanation Establishes a "wait" status until axis movement of the robot specified by the <robot number> is completed (within the positioning tolerance range.)The <robot number> can be omitted. If it is omitted, robot 1 is specified.

> If a specific axis of the specified robot has been specified by the <axis number>, this command will apply only to that axis. If there is no <axis number> setting, this command applies to all axes of the specified robot.

SAMPLE

WAIT ARM ..... Waits for the movement completion of robot 1. for the movement

WAIT ARM[2](2)......Waits completion of axis 2 of robot 2.

Related commands

DRIVE, DRIVEI, MOVE, MOVEI

Q

### **WEIGHT**

Specifies/acquires the tip weight parameter

### **Format**

WEIGHT [<robot number>] <expression>

Values

<robot number>.....1 to 4

<expression>.....The range varies according to the robot which has been specified.

Explanation Changes the tip weight parameter of the robot specified by the <robot number> to the <expression> value. The <robot number> can be omitted. If it is omitted, robot 1 is specified. This change does not apply to auxiliary axes.

### Functions

### **Format**

WEIGHT [<robot number>]

Values

<robot number>......1 to 4

Explanation Acquires the tip weight parameter value of the robot specified by the <robot number>.

The <robot number> can be omitted. If it is omitted, robot 1 is specified.

### SAMPLE

A=5

B=2

C=WEIGHT

WEIGHT A

MOVE P, P0

WEIGHT B

MOVE P, P1

WEIGHT C

D=WEIGHT ..... The tip weight parameter of robot 1 is assigned to variable D.

HALT

\_

Q

R

S

W

X

```
Format
```

```
WHILE <conditional expression>
  <command block>
WEND
```

Explanation Ends the command block which begins with the WHILE statement. A WEND statement must always be paired with a WHILE statement.

Jumping out of the WHILE to WEND loop is possible by using the GOTO statement,

```
SAMPLE
```

```
A=0
WHILE DI3(0)=0
   A=A+1
   MOVE P, P0
   MOVE P,P1
   PRINT "COUNTER=";A
WEND
HALT
```

Related commands

WHILE

WEND **7-181** 

### **WHERE**

Acquires the arm's current position (pulse coordinates)

### **Format**

WHERE [<robot number>]

Values

<robot number>......1 to 4

Explanation Acquires the arm's current position of the robot specified by the <robot number> in joint coordinates. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

### SAMPLE

P10=WHERE ..... The current position's pulse coordinate value is assigned to P10.

Related commands

**WHRXY** 

### WHILE to WEND

Repeats an operation for as long as a condition is met

### **Format**

```
WHILE <conditional expression> <command block> WEND
```

### **Explanation**

Executes the command block between the WHILE and WEND statements when the condition specified by the <conditional expression> is met, and then returns to the WHILE statement to repeat the same operation.

When the <conditional expression> condition is no longer met (becomes false), the program jumps to the next command after the WEND statement.

If the <conditional expression> condition is not met from the beginning (false), the command block between the WHILE and WEND statements is not executed, and a jump occurs to the next statement after the WEND statement.

Jumping out of the WHILE to WEND loop is possible by using the GOTO statement, etc.



• When the conditional expression is a numeric expression, an expression value other than "0" indicates a TRUE status, and "0" indicates a FALSE status.

### SAMPLE 1

```
A=0
WHILE DI3(0)=0
A=A+1
MOVE P,P0
MOVE P,P1
PRINT "COUNTER=";A
WEND
HALT
```

```
SAMPLE 2
```

N

0

P

Q

R

S

. ,

W

X

Y

### **WHRXY**

Acquires the arm's current position in Cartesian coordinates

### **Format**

WHRXY [<robot number>]

Values <robot number>......1 to 4

v violot numbers ......

Explanation Acquires the arm's current position of the robot specified by the <robot number> in Cartesian coordinates. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

On YK500TW model robots, the X-arm and Y-arm rotation information is also set.

### SAMPLE

P10=WHRXY ..... The current position Cartesian coordinate value of robot 1 is assigned to P10.

Related commands

WHERE

0

P

Q

R

S

Т

U

\A/

Χ

Y

Z

Converts the Cartesian coordinate data ("mm") to joint coordinate data ("pulse")

### **Format**

XYTOJ [<robot number>] (<point expression>)

Values

<robot number>......1 to 4

**Explanation** 

This function converts the Cartesian coordinate data (unit: mm, deg.) specified by the <point expression> to joint coordinate data (unit: pulse) of the robot specified by the <robot number>. The <robot number> can be omitted. If it is omitted, robot 1 is specified.

- When the command is executed, the data is converted based on the standard coordinates, shift coordinates and hand definition that were set.
- On SCARA robots, the converted result differs depending on whether right-handed or left-handed is specified.
- On the YK500TW model robot, the result varies, depending on the X-arm and Y-arm rotation information settings.
- To convert joint coordinate data to Cartesian coordinate data, use the JTOXY statement.

### SAMPLE

P10=XYTOJ(P10) ····· P10 is converted to joint coordinate data.

N

0

P

Q

R

ς

Т

X

Y

Z

# Chapter 8 Data file description

1	Overview	8-1
2	Program file	8-2
3	Point file	8-4
4	Point comment file	8-8
5	Parameter file	8-10
6	Shift coordinate definition file	8-13
7	Hand definition file	8-15
8	Pallet definition file	8-17
9	All file	8-21
10	Program directory file	8-22
11	Parameter directory file	8-24
12	Variable file	8-25
13	Constant file	8-28
14	Array variable file	8-29
15	DI file	8-31
16	DO file	8-33
17	MO file	8-35
18	LO file	8-37

19	TO file	8-39
20	SI file	8-41
21	SO file	8-43
22	EOF file	8-45
23	Serial port communication file	8-46
24	SIW file	8-47
25	SOW file	8-49
26	Ethernet port communication file	8-51

### Data file types 1.1

This section explains data files used with a SEND statement and READ/WRITE online commands. There are 25 different types of data files.

- Program file 1.
- 2. Point file
- Point comment file 3.
- 4. Parameter file
- Shift coordinate definition file 5.
- Hand definition file 6.
- Pallet definition file 7.
- All file 8.
- 9. Program directory file
- 10. Parameter directory file
- Variable file 11.
- 12. Constant file
- 13. Array variable file
- 14. DI file
- 15. DO file
- 16. MO file
- LO file
- 18. TO file
- SI file 19.
- 20. SO file
- 21. EOF file
- Serial port communication file 22.
- SIW file 23.
- SOW file 24.
- 25. Ethernet port communication file

### 1.2 **Cautions**

Observe the following cautions when handling data files.

- Only 1-byte characters can be used.
- All data is handled as character strings conforming to ASCII character codes.
- Only upper case alphabetic characters may be used in command statements (lower case characters are prohibited).
- Line lengths must not exceed 255 characters.
- A [cr/lf] data format designation indicates CR code (0Dh) + LF code (0Ah).
- The terms "reading" and "writing" used in this manual indicate the following data flow directions: Reading: controller → external communication device

Writing: External communication device → controller

## 2 Program file

### 2.1 All programs

### **Format**

PGM

### Meaning

- Expresses all programs.
- When used as a readout file, all programs currently stored are read out.
- If there is a specification of a program number in the case of a write file, the new program overwrites.
- If the program number is omitted in the case of a write file, the assignment is made to the smallest free number. If there are programs with the same name and with different program numbers, the oldest program is deleted.

# DATA FORMAT NAME = <program name> [cr/lf] PGN=mmm aaaaa ...aaaaaaaaaaaaaaa[cr/lf] : aaaaa ...aaaaaaaaaaaaaaa[cr/lf] : NAME = <program name> [cr/lf] PGN=mmm aaaaa ...aaaaaaaaaaaaaaa[cr/lf] : aaaaa ...aaaaaaaaaaaaaaa[cr/lf] [cr/lf]

### Values

```
a ......Character code
mmm ......Program number: 1 to 100
```

- <Program names> are shown with 32 characters or less consisting of alphanumeric characters and underscore (\_).
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SEND PGM TO CMU······ Outputs all programs from communication port.

SENDCMU TO PGM ····· Inputs all programs from communication port.

Response:
NAME=TEST[cr/lf]
PGN=1
A=1[cr/lf]
RESET DO2()[cr/lf]
:
HALT[cr/lf]
[cr/lf]
```

Ш

### **Format**

- 1.cprogram name>
- 2. PGmmm

### Meaning

- Expresses a specified program.
- "mmm" is 1 to 100.
- Program name may be up to 32 characters consisting of alphanumeric characters and underscore "\_" and must be enclosed by "<" and ">".
- If no program name is specified in format 1, the currently selected program is specified.
- An error occurs if the specified program name differs from the program name on the data.

### DATA FORMAT



```
a ......Character code
mmm ......Program name:1 to 100
```

- <Program names> are shown with 32 characters or less consisting of alphanumeric characters and underscore (\_).
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.



• At program writing operations, be sure to use the NAME statement to specify the program name. Program writing cannot occur if the program name is not specified.

- Writing into the currently selected program is not possible.
- When a sequence program is being executed, writing into the program name "SEQUENCE" is not possible.

### SAMPLE

```
SEND <TEST1> TO CMU······· Outputs the program "TEST1" from communication port.

SEND CMU TO <TEST1>···· Inputs the program "TEST1" from communication port

Response:

NAME=TEST1[cr/lf]
A=1[cr/lf]
RESET DO2()[cr/lf]
:
HALT[cr/lf]
[cr/lf]
```

3.1

## All points

### **Format**

PNT

Point file

### Meaning

- Expresses all point data.
- When used as a readout file, all points currently stored are read out.
- When used as a write file, writing is performed with a point number.

### DATA FORMAT (On robots other than YK500TW)

```
Pmmmm=fxxxxxx fyyyyyy fzzzzz frrrrr faaaaaa fbbbbbb t[cr/lf]
Pmmmm=fxxxxxx fyyyyyy fzzzzz frrrrr faaaaaa fbbbbbb t[cr/lf]
:
Pmmmm=fxxxxxx fyyyyyy fzzzzz frrrrr faaaaaa fbbbbbb t[cr/lf]
Pmmmm=fxxxxxx fyyyyyy fzzzzzz frrrrr faaaaaa fbbbbbb t[cr/lf]
[cr/lf]
```

### DATA FORMAT (On robot YK500TW)

```
Pmmmm= fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr [cr/lf]
Pmmmm= fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr [cr/lf]

:

Pmmmm= fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr [cr/lf]

Pmmmm= fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr [cr/lf]

[cr/lf]
```



### NOTE

 Integer point data is recognized in pulse units, and real number point data is recognized in "mm" units.



mmmm ...... Point No.: 0 to 29999

f ......Coordinate sign: + / - / space

xxxxxx/../bbbbbb .... Represent a numeric value of 8 digits or less. When a dot is included, this is treated as point data in "mm" units. Each piece of data is separated by one or more spaces.

t ......Extended hand system flag setting for SCARA robots. 1: right hand system; 2: left hand system.

xr ...... Extended setting's first arm rotation information.

0: The "mm  $\rightarrow$  pulse" converted angle data x (\*1) range is  $-180.00^{\circ}$  < x < =  $180.00^{\circ}$ .

1: The "mm  $\rightarrow$  pulse" converted angle data x (\*1) range is 180.00° < x < = 540.00°.

-1: The "mm  $\rightarrow$  pulse" converted angle data x (\*1) range is -540.00° < x < = -180.00°.

yr ...... Extended setting's second arm rotation information.

0: The "mm  $\rightarrow$  pulse" converted angle data x (\*1) range is  $-180.00^{\circ}$  < y < =  $180.00^{\circ}$ .

1: The "mm  $\rightarrow$  pulse" converted angle data x (\*1) range is  $180.00^{\circ} < y < = 540.00^{\circ}$ .

-1: The "mm  $\rightarrow$  pulse" converted angle data x (\*1) range is -540.00° < y < = -180.00°.

\*1: The joint-coordinates-converted pulse data represents each arm's distance (converted to angular data) from its mechanical origin point.

- Hand system flags are valid only for SCARA robots, with the coordinate data specified in "mm" units.
- If a number other than "1" or "2" is specified for a hand system flag, or if no number is specified, this is interpreted as "0" setting (no hand system flag).

- The first arm and the second arm rotation information settings are available only on the YK500TW robot model where a "mm" units coordinate system has been set.
- The first arm and the second arm rotation information is processed as "0" if a numeral other than 0, 1, -1 has been specified, or if no numeral has been specified.
- A line containing only [cr/lf] is added at the end of the file to indicate the end of the file.

SAMPLE (On ro	bots oth	ner than	YK500T	W)		
SEND PNT TO C	CMU ·····		utputs mmunica	_		from
SEND CMU TO I	PNT·····	I r		all p	oints	from
Response:						
P0 = 1	2	3	4	5	6	[cr/lf]
P1 = 1.00	2.00	3.00	4.00	5.00	6.00	[cr/lf]
P2 = 1.00	0.00	0.00	0.00	0.00	0.00	[cr/lf]
:						
P29999=-1.00 [cr/lf]	0.00	0.00	0.00	0.00	0.00	[cr/lf]

SAMPLE (On robot YK!	500TW)				
SEND PNT TO CMU·····	-		-	nts	from
SEND CMU TO PNT······	Inpu	nication p ts all nication p	poi	nts	from
Response:					
P0 = 1 2	3	4 5		6	[cr/lf]
P1 = 426.20 -160.77	0.01 337.21	0.00 0.00	0	1 0	[cr/lf]
P2 = -27.57 - 377.84	0.36 193.22	0.00 0.00	0 -	1 0	[cr/lf]
:					
P29999=-251.66 -419.51 [cr/lf]	0.00 -127.79	0.00 0.00	2 -	1 -1	[cr/lf]

# 3.2

## One point

### **Format**

**Pmmmm** 

### Meaning

- Expresses a specified point.
- "mmmm" must be from 0 to 29999

### DATA FORMAT (On robots other than YK500TW)

Pmmmm=fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]

### DATA FORMAT (On robot YK500TW)

Pmmmm= fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr [cr/lf]

### Values

- xxxxxx/../bbbbbb .... Represent a numeric value of 8 digits or less. When a dot is included, this is treated as point data in "mm" units. Each piece of data is separated by one or more spaces.
- t ...... Extended hand system flag setting for SCARA robots. 1: right hand system; 2: left hand system.
- xr ...... The first arm rotation information for the YK500TW robot.
  - 0: The "mm  $\rightarrow$  pulse" converted pulse data x (\*1) range is  $-180.00^{\circ}$  < x < =  $180.00^{\circ}$ .
  - 1: The "mm  $\rightarrow$  pulse" converted pulse data x (\*1) range is  $180.00^{\circ} < x < = 540.00^{\circ}$ .
  - -1: The "mm  $\rightarrow$  pulse" converted pulse data x (\*1) range is -540.00° < x < = -180.00°.
- - 1: The "mm  $\rightarrow$  pulse" converted pulse data x (\*1) range is 180.00° < y < = 540.00°.
- -1: The "mm  $\rightarrow$  pulse" converted pulse data x (\*1) range is -540.00° < y < = -180.00°. \*1: The joint-coordinates-converted pulse data represents each arm's distance (converted to
- angular data) from its mechanical origin point.
- Hand system flags are valid only for SCARA robots, with the coordinate data specified in "mm" units.
- If a number other than "1" or "2" is specified for a hand system flag, or if no number is specified, this is interpreted as "0" setting (no hand system flag).
- The first arm and the second arm rotation information settings are available only on the YK500TW robot model where a "mm" units coordinate system has been set.
- The first arm and the second arm rotation information is processed as "0" if a numeral other than 0,
   1, -1 has been specified, or if no numeral has been specified.



 Integers indicate point data in "pulse" units, and real numbers in "mm" units.

SAMPLE (On robots other than YK500TW)
SEND P100 TO CMU······ Outputs the specified point from communication port.
SEND CMU TO P100 Inputs the specified point from communication port.
Response: P100= 1 2 3 4 5 6[cr/lf]

SAMPLE (On robo	t YK50	OTW)						
SEND P100 TO CM	Ι <b>υ·····</b>	• • • • • •	_			speci ation		_
SEND CMU TO P10	0	• • • • • •	_		_	ecified port.	_	nt from
Response: P100= 1 2	3	4	5	6	0	1	0	[cr/lf]

### 4 Point comment file

### 4.1 All point comments

### **Format**

PCM



- Expresses all point comments.
- When used as a readout file, all point comments currently stored are read out.
- When used as a write file, writing is performed with a point comment number.

### 

Values

[cr/lf]

mmmm .......Point comment number: a number from 0 to 29999 ss...ss......Comment data: which can be up to 16 one-byte characters. If comment data exceeds 16 characters, then the 17th character onwards will be deleted.

A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SEND PCM TO CMU....... Outputs all point comments from communication port.

SEND CMU TO PCM....... Inputs all point comments from communication port.

Response:
PC1 = ORIGIN POS[cr/lf]
PC3 = WAIT POS[cr/lf]
:
PC3999 = WORK100[cr/lf]
[cr/lf]
```

### 4.2 One point comment

### **Format**

**PCmmmm** 

### Meaning

- Expresses a specified point comment.
- "mmmm" represents a number from 0 to 29999.

### DATA FORMAT

PCmmmm= ssssssssssssss[cr/lf]

Values

### SAMPLE

SEND PC1 TO CMU ...... Outputs the specified point comment from communication port.

SEND CMU TO PC1 ..... Inputs the specified point comment from communication port.

### Response:

PC1 = ORIGIN POS[cr/lf]

8

9

10

11

5

### Parameter file

### 5.1 All parameters

### **Format**

PRM

### Meaning

- Expresses all parameters (including settings in "UTILITY" mode).
- When used as a readout file, all parameters currently stored are read out.
- When used as a write file, only the parameters specified by parameter labels are written.

# /parameter label/ ' <comment> [cr/lf] RC= xxxxxx [cr/lf] /parameter label/ ' <comment> [cr/lf] R1= xxxxxx R2= yyyyyy [cr/lf] /parameter label/ ' <comment> [cr/lf] R1= xxxxxx, yyyyyy, zzzzzz, rrrrrr[cr/lf] /parameter label/ ' <comment> [cr/lf] /parameter label/ ' <comment> [cr/lf] : [cr/lf]

### Values

- Parameter labels are shown with 8 alphabetic characters.
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.



- When writing parameter data, be sure that the servo is off.
- Parameters are already compatible with upper versions. However, parameters might not always be compatible with lower versions (upward compatibility).
- When you attempt to load a parameter file of new version into a controller of an earlier version, an error "10.14: Undefined parameter found" may appear. If this happens, you may load the parameter by setting the "Skip undefined parameters" parameter to "VALID". For more details, refer to the "SYSTEM mode" "Parameters" section in the robot controller user's manual. For more details, refer to the "SYSTEM mode" "Other parameters" section in the robot controller user's manual.

```
8
```

9

10

u.

```
SAMPLE
SEND PRM TO CMU·····Outputs all parameters from
                       communication port.
SEND CMU TO PRM .....Inputs all parameters from
                       communication port.
Response:
' V1.01/R0001
' V1.01/V1.01/V1.01/V1.01/V1.01/V1.01/V1.01/
' ----/----/----/
/RBTNUM/[cr/lf]
R1 = 3000 R2 = 3010 [cr/lf]
/AXSNUM/[cr/lf]
R1A= 5000, 5001, 5010, 5011 [cr/lf]
R2A = 0, 0, 0,
                           0 [cr/lf]
/ATTRIB/
R1A= 33792, 33792, 33792, 33792 [cr/lf]
R1A= 256, 256, 256, 256 [cr/lf]
/WEIGHT/ '[kg][cr/lf]
R1= 2 R2= 12 [cr/lf]
[cr/lf]
```

### 5.2 One parameter

### **Format**

/parameter label/

### Meaning

- Parameter labels are shown with 8 alphabetic characters.
- · When used as a readout file, only the parameter specified by a parameter label is
- When used as a write file, only the parameter specified by a parameter label is written.

### DATA FORMAT 1

```
/parameter label/ ' <comment>[cr/lf]
RC= xxxxxx [cr/lf]
[cr/lf]
```

### DATA FORMAT 2

```
/parameter label/ ' <comment>[cr/lf]
R?= xxxxxx [cr/lf]
[cr/lf]
```

### DATA FORMAT 3

```
/parameter label/ ' <comment>[cr/lf]
R?= xxxxxx,xxxxxxx,xxxxxx[cr/lf]
[cr/lf]
```

### **Values**

```
RC.....Indicates the entire controller.
R?.....Robot setting: ?: robot number
A......Represents an axis parameter. Data on each axis is
                    separated by a comma.
<Comment> ......Parameter name
```

- Parameter labels are shown with 8 alphabetic characters.
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.



- When writing parameter data, be sure that the servo is off.
- Parameters are already compatible with upper versions. However, parameters might not always be compatible with lower versions (upward compatibility).

 When you attempt to load a parameter file of new version into a controller of an earlier version, an error "10.14: Undefined parameter found" may appear.

### SAMPLE

```
/ACCEL / TO CMU ····· Outputs the acceleration parameter
SEND
                            from communication port.
SEND CMU TO /ACCEL / ...... Inputs the acceleration parameter
                            from communication port.
Response:
/ACCEL / '[%]
                                100 [cr/lf]
R1A=
      100,
               100,
                      100,
[cr/lf]
```

### All shift data 6.1

**Format** SFT

### Meaning

- Expresses all shift data.
- When used as a readout file, all shift data currently stored are read out.
- When used as a write file, writing is performed with a shift number.

```
DATA FORMAT
    = fxxxxxx
                         fzzzzzz frrrrrr [cr/lf]
               fyyyyyy
SPm = fxxxxxx
                                  frrrrrr [cr/lf]
                         fzzzzzz
               fyyyyyy
SMm = fxxxxxx
                         fzzzzzz
                                  frrrrrr [cr/lf]
               fyyyyyy
Sm = fxxxxx
                                  frrrrrr [cr/lf]
               fyyyyyy
                         fzzzzzz
SPm = fxxxxxx
                                  frrrrrr [cr/lf]
               fyyyyyy
                         fzzzzzz
SMm = fxxxxx
                                  frrrrrr [cr/lf]
               fyyyyyy
                         fzzzzzz
[cr/lf]
```

Values

```
m ......Shift No.: 0 to 9
f ......Coordinate sign: + / - / space
xxxxxx/yyyyyy/../rrrrrr ...........Represent a numeric value of 8 digits or less, having 2
                         or less places below the decimal point.
```

- The SPm and SMm inputs are optional in writing files. SPm: shift coordinate range plus-side; SMm: shift coordinate range minus-side
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND SFT TO CMU······Outputs all shift data from
                           communication port.
SEND CMU TO SFT ..... Inputs all shift data from
                           communication port.
Response:
                              0.00 [cr/lf]
S0 =
               0.00
                       0.00
        0.00
                              0.00 [cr/lf]
SP0=
        0.00
               0.00
                       0.00
SM0=
                              0.00 [cr/lf]
        0.00
               0.00
                       0.00
S1 =
        1.00
               1.00
                       1.00
                              1.00 [cr/lf]
SM39=
        9.00
                              9.00 [cr/lf]
               9.00
                       9.00
[cr/lf]
```

### 6.2 One shift definition

### **Format**

Sm

Meaning • Expresses a specified shift definition.

### DATA FORMAT

Sm = fxxxxxx fyyyyyy fzzzzzz frrrrrr[cr/lf]

Values m ......Shift No.: 0 to 39

f ......Coordinate sign: + / - / space

xxxxxx/yyyyyy/../rrrrrr ...........Represent a numeric value of 8 digits or less, having 2 or less places below the decimal point.

### SAMPLE

SEND SO TO CMU ...... Outputs the specified shift coordinate from communication port.

SEND CMU TO S0  $\cdots\cdots\cdots$  Inputs the specified shift coordinate from communication port.

### Response:

S0 =0.00 0.00 0.00 0.00 [cr/lf] SP0=0.00 0.00 0.00 0.00 [cr/lf] SM0=0.00 0.00 0.00 0.00 [cr/lf] [cr/lf]

### 7.1 All hand data

### **Format**

HND

### Meaning

- Expresses all hand data.
- When used as a readout file, all hand data currently stored are read out.
- When used as a write file, writing is performed with a hand number.

```
DATA FORMAT

Hm = n,fxxxxxx, fyyyyyy, fzzzzzz [,{R}][cr/lf]
:

Hm = n,fxxxxxx, fyyyyyy, fzzzzzz [,{R}][cr/lf]
[cr/lf]
```

### Values

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND HND TO CMU·····Outputs all hand data from
                           communication port.
SEND CMU TO HND ..... Inputs all hand data from
                           communication port.
Response:
                  0.00,
H0 = 1,
                          0.00 [cr/lf]
          0.00,
    1,
H1 =
          1.00,
                  1.00,
                          1.00 [cr/lf]
      2,
          2.00,
                  2.00,
                          2.00 [cr/lf]
                          3.00 [cr/lf]
H3 = 2,
          3.00,
                  3.00,
                          4.00 [cr/lf]
H4 = 3,
          4.00,
                  4.00,
                          5.00 [cr/lf]
H5 = 3,
          5.00,
                  5.00,
H6 = 4,
                  6.00,
                          6.00 [cr/lf]
          6.00,
H7 = 4
                          7.00 [cr/lf]
          7.00,
                  7.00,
[cr/lf]
```

### 7.2 One hand definition

### **Format**

Hm

Meaning • Expresses a specified hand definition.

### DATA FORMAT

 $Hm = n, fxxxxxx, fyyyyyy, fzzzzzz[,{R}][cr/lf]$ 

Values

### SAMPLE

SEND H3 TO CMU ...... Outputs the specified hand definition data from communication port.

SEND CMU TO H3 ..... Inputs the specified hand definition data from communication port.

### Response:

H3 = 2, 3.00, 3.00, 3.00 [cr/lf]

### All pallet definitions 8.1

### **Format**

PLT

- Expresses all pallet definitions.
- When used as a readout file, all pallet definitions currently stored are read out.
- When used as a write file, writing is performed with a pallet number.

```
DATA FORMAT (On robots other than YK500TW)
PLm [cr/lf]
PLN = XY [cr/lf]
NX
      nnn [cr/lf]
       nnn [cr/lf]
NY
NZ = nnn [cr/lf]
PLP = ppppp [cr/lf]
P[1] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]
P[5] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]
PLm [cr/lf]
[cr/lf]
```

```
DATA FORMAT (On robot YK500TW)
PLm [cr/lf]
PLN = XY [cr/lf]
    = nnn [cr/lf]
NY
       nnn [cr/lf]
    = nnn [cr/lf]
PLP = ppppp [cr/lf]
P[1] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr[cr/lf]
P[5] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr[cr/lf]
PLm [cr/lf]
[cr/lf]
```

```
Values
         m ...... Pallet number: 0 to 39
         ppppp ......The point number used for a pallet definition.
                                  Continuous 5 points starting with the specified point are used.
         f ...... Coordinate sign: + / - / space
         xxxxxx/yyyyyy/../bbbbbb......
                       Represent a numeric value of 8 digits or less. When a dot is included,
                       this is treated as coordinate data in "mm" units. Each piece of data is
                       separated by one or more spaces.
         t ...... An extended hand system flag setting for SCARA robots. 1: Right-
```

handed system, 2: Left-handed system

```
xr ...... Extended setting for the first arm rotation information. 

0: "mm" \rightarrow pulse converted angle data x (*1) range: -180.00° < x <= 180.00° 

1: "mm" \rightarrow pulse converted angle data x (*1) range: 180.00° < x <= 540.00° 

-1: "mm" \rightarrow pulse converted angle data x (*1) range: -540.00° < x <= -180.00° 

yr ...... Extended setting for the second arm rotation information. 

0: "mm" \rightarrow pulse converted angle data x (*1) range: -180.00° < y <= 180.00° 

1: "mm" \rightarrow pulse converted angle data x (*1) range: 180.00° < y <= 540.00°
```

-1: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: -540.00° < y <= -180.00°

- \*1: The joint-coordinates-converted pulse data represents each arm's distance (converted to angular data) from its mechanical origin point.
- Hand system flags are enabled only when specifying the coordinate data in "mm" units for SCARA robots.
- Hand system flags and the first arm and the second arm rotation information are ignored during movement where pallet definitions are used.
- If a number other than 1 or 2 is set, or if no number is designated, then 0 will be set to indicate that there is no hand system flag.
- The first arm and the second arm rotation information settings are available only on the YK500TW robot model where a "mm" units coordinate system has been set.
- If a value other than "0", "1", "-1" is specified at the first arm and the second arm rotation information, or if no value is specified, this will be processed as "0".
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND PLT TO CMU······Outputs all pallet definitions
                             from communication port.
SEND CMU TO PLT...... Inputs all pallet definitions
                            from communication port.
Response:
PL0[cr/lf]
PLN=XY[cr/lf]
NX =
      3[cr/lf]
NY =
      4[cr/lf]
      2[cr/lf]
NZ =
PLP= 3996[cr/lf]
P[1]=
        0.00
                        0.00
                                0.00
                                                       [cr/lf]
                0.00
                                        0.00
                                                0.00
P[2] = 100.00
                0.00
                                0.00
                                        0.00
                                                       [cr/lf]
                        0.00
                                                0.00
        0.00 100.00
                                                       [cr/lf]
P[3] =
                        0.00
                                0.00
                                        0.00
                                                0.00
P[4] = 100.00
             100.00
                        0.00
                                0.00
                                        0.00
                                                0.00
                                                       [cr/lf]
P[5] =
        0.00
                0.00
                       50.00
                                0.00
                                        0.00
                                                0.00
                                                       [cr/lf]
PL1[cr/lf]
PLN= XY[cr/lf]
NX = 3[cr/lf]
NY =
      4[cr/lf]
NZ =
      2[cr/lf]
PLP= 3991[cr/lf]
P[1] =
        0.00
                        0.00
                                0.00
                                        0.00
                                                0.00
                                                       [cr/lf]
                0.00
P[2] = 100.00 100.00
                        0.00
                                0.00
                                        0.00
                                                0.00
                                                       [cr/lf]
P[3] =
        0.00 200.00
                        0.00
                                0.00
                                                0.00
                                                       [cr/lf]
                                        0.00
P[4] = 100.00 200.00
                        0.00
                                0.00
                                        0.00
                                                0.00
                                                       [cr/lf]
P[5] =
        0.00
                0.00
                      100.00
                                0.00
                                        0.00
                                                0.00
                                                       [cr/lf]
[cr/lf]
```

PLm

### Meaning

- Expresses a specified pallet definition.
- "m" must be from 0 to 39.

```
DATA FORMAT (On robots other than YK500TW)

PLm [cr/lf]
PLN = XY [cr/lf]
NX = nnn [cr/lf]
NY = nnn [cr/lf]
NZ = nnn [cr/lf]
PLP = ppppp [cr/lf]
P[1] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]
:
P[5] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]
[cr/lf]
```

# DATA FORMAT (On robot YK500TW) PLm [cr/lf] PLN = XY [cr/lf] PLP = ppppp [cr/lf] NX = nnn [cr/lf] NY = nnn [cr/lf] NZ = nnn [cr/lf] P[1] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr[cr/lf] : P[5] = fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t xr yr[cr/lf] [cr/lf]

# -

### NOTE

 Integers indicate point data in "pulse" units, and real numbers in "mm" units.

aluos	m	Pallet	number:	O to	30
alues	m	rallet	number:	U to	39

nnn ...... Number of points for each axis: positive integer

ppppp ...... The point number used for a pallet definition. Continuous 5 points starting with the specified point are used.

f ...... Coordinate sign: + / - / space

xxxxxx/yyyyyy/../bbbbbb.......

Represent a numeric value of 8 digits or less. When a dot is included, this is treated as point data in "mm" units. Each piece of data is separated by one or more spaces.

t ...... An extended hand system flag setting for SCARA robots. 1: Right-handed system, 2: Left-handed system

xr ...... Extended setting for the first arm rotation information.

0: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: -180.00° < x <= 180.00°

1: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: 180.00° < x <= 540.00°

-1: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: -540.00° < x <= -180.00°

yr ....... Extended setting for the second arm rotation information.

0: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: -180.00° < y <= 180.00°

1: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: 180.00° < y <= 540.00°

-1: "mm"  $\rightarrow$  pulse converted angle data x (\*1) range: -540.00° < y <= -180.00°

- \*1: The joint-coordinates-converted pulse data represents each arm's distance (converted to angular data) from its mechanical origin point.
- Hand system flags are enabled only when specifying the coordinate data in "mm" units for SCARA robots.
- Hand system flags and the first arm and the second arm rotation information are ignored during movement where pallet definitions are used.
- If a number other than 1 or 2 is set, or if no number is designated, then 0 will be set to indicate that there is no hand system flag.
- The first arm and the second arm rotation information settings are available only on the YK500TW robot model where a "mm" units coordinate system has been set.
- If a value other than "0", "1", "-1" is specified at the first arm and the second arm rotation information, or if no value is specified, this will be processed as "0".
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

SAMPLE					
SEND PL2 TO CMU·		utputs the	-	-	
SEND CMU TO PL2.	I	rom communion puts the s rom communion	pecified	pallet d	efinition
Response:					
PL2[cr/lf]					
PLN=XY[cr/lf]					
NX = 3[cr/lf]					
NY= 3[cr/lf]					
NZ= 2[cr/lf]					
PLP= 3986[cr/lf]					
P[1] = 100.00 100	.00 50.00	90.00	0.00	0.00	[cr/lf]
P[2] = 200.00 100	.00 50.00	90.00	0.00	0.00	[cr/lf]
P[3] = 100.00 200	.00 50.00	90.00	0.00	0.00	[cr/lf]
P[4] = 200.00 200	.00 50.00	90.00	0.00	0.00	[cr/lf]
P[5] = 100.00 10	.00 100.00	90.00	0.00	0.00	[cr/lf]
[cr/lf]					

### 9.1 All files

### **Format**

ALL

Meaning Expresses the minimum number of data files required to operate the robot system.

# NOTE

 For details of each file, refer to that file's explanation.

### DATA FORMAT

```
[PGM] All program format
NAME=< program name >
[cr/lf]
[PNT] All point format
Pmmmm=fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]
Pmmmm=fxxxxxx fyyyyyy fzzzzzz frrrrrr faaaaaa fbbbbbb t[cr/lf]
[cr/lf]
[PCM] All point comment format
PCmmmm= ssssssssssssss[cr/lf]
PCmmmm= sssssssssssss[cr/lf]
[cr/lf]
[PRM] All parameter format
/parameter label/'<comment> [cr/lf]
RC= xxxxxx [cr/lf]
/parameter label/'<comment> [cr/lf]
R1= xxxxxx R2= yyyyyy [cr/lf]
[cr/lf]
[END] ALL files end
```



• In writing files, [xxx] determines the data file's format, and this format is saved at the controller. Example: [HND]...All text data up the next [xxx] is saved at the controller as "all hand" format data.

	F.	ы	а	Б	B	ě	W.	Œ	M	a	r
	-7	P	н	μ	ы	Ŧ	¥	ų.	٧÷	»)	r

```
SEND ALL TO CMU·······Outputs all files of the entire system from communication port.

SEND CMU TO ALL·····Inputs all files of the entire system from communication port.
```

### 10 Program directory file

### 10.1 **Entire program directory**

### Format

DIR

### Meaning

- Expresses entire program directory.
- When used as a readout file, information on entire program directory is read out.
- Cannot be used as a write file.

DATA FORMAT					
No. Name nnnfgsssssss		Byte bbbbbb	RW/RO		Time[cr/lf] hh:mm[cr/lf]
nnnfgsssssss END[cr/lf]	1111	bbbbbb	xx	yy/mm/dd	hh:mm[cr/lf]

Values

nnn	Program directory number: 3 digits					
f	"o" at program compiling when a program object is					
	created. "s" at sequence program compiling when a					
	sequence object is created.					
g	Shows an asterisk "*" for the currently selected program.					
SSSSSSS	sssssssProgram name: 32 digits					
IIII	Number of program lines: 4 digits					
bbbbbb	.Byte size of program: 6 digits					
xxFile attribute: 2 digits						
	RW: Readable/writable					
	RO: Not writable (read only)					
yy/mm/dd	.Date when the program was updated: 8 digits (including					
	the "/" marks)					
hh:mm	Time when the program was updated: 5 digits					

SAMP	SAMPLE											
SEND	SEND DIR TO CMU······Outputs information on all program											
	directory from communication port.											
Resp	Response:											
No.	Name	Line	Byte	RW/R	20 Date	Time[cr/lf]						
10*	12345678	5	21	RW	01/06/20	10:35[cr/lf]						
2	PGM1	5	66	RW	01/06/20	10:35[cr/lf]						
3	PGM2	5	66	RW	01/06/20	10:35[cr/lf]						
4	PGM3	5	66	RW	01/06/20	10:35[cr/lf]						
5	PGM4	5	66	RW	01/06/20	10:35[cr/lf]						
6	PGM5	5	66	RW	01/06/20	10:35[cr/lf]						
7	PGM6	5	66	RW	01/06/20	10:35[cr/lf]						
88	SEQUENCE	1	15	RW	01/06/20	10:35[cr/lf]						
END[cr/lf]												

#### **Format**

"<<" <pre>" <>" >>"

#### **Meaning**

- Expresses information on one program.
- The program name is enclosed in <<>> double brackets.

DATA	FORMAT

No. Name Line Byte RW/RO Date Time[cr/lf] nnnfgsssssss 1111 bbbbbb xx yy/mm/dd hh:mm[cr/lf]



nnnProgram directory number: 3 digits
f"o" at program compiling when a program object is
created. "s" at sequence program compiling when a
sequence object is created.
gShows an asterisk $^{"*"}$ for the currently selected program.
ssssssssProgram name: 32 digits
IIIINumber of program lines: 4 digits
bbbbbbByte size of program: 6 digits
xxFile attribute: 2 digits
RW: Readable/writable
RO: Not writable (read only)
yy/mm/ddDate when the program was updated: 8 digits (including
the "/" marks)
hh:mmTime when the program was updated: 5 digits



• Indicates the compiled execution program (program objects compiled for a robot program, or sequence objects compiled for a sequence program).

#### SAMPLE

SEND <<TEST>> TO CMU  $\cdots$  Outputs information on the specified program from communication port.

## Response:

No. Name Line Byte RW/RO Date Time[cr/lf] 30\* PGM2 5 66 RW 01/06/20 10:35[cr/lf]

#### Parameter directory file 11

#### **Entire parameter directory** 11.1

#### **Format**

DPM



- Meaning Expresses entire parameter directory.
  - When used as a readout file, information on entire parameter directory is read out.
  - Cannot be used as a write file.

```
DATA FORMAT
/parameter label/ ' <comment>[cr/lf]
/parameter label/ ' <comment>[cr/lf]
/parameter label/ ' <comment>[cr/lf]
 [cr/lf]
```

**Values** 

<comment> ...... Parameter name

- Parameter labels are shown with 6 alphabetic characters.
- A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND DPM TO CMU······Outputs information on all parameter
                           directory from communication port.
Response:
/RBTNUM/ 'Robot number (V8.01/R1001) [cr/lf]
/AXES / 'Number of axes[cr/lf]
/AXSNUM/ 'Axis number(V1.01/V1.01/V1.01/V1.01/----/) [cr/lf]
/ATTRIB/ 'Axis attribute[cr/lf]
/WEIGHT/ 'Tip weight[kg][cr/lf]
/ORIGIN/ 'Origin sequence[cr/lf]
/RORIEN/ 'R axis orientation[cr/lf]
/CURPNO/ 'Output port number[cr/lf]
/CURPT1/ 'Number of compare point 1[cr/lf]
/CURPT2/ 'Number of compare point 2[cr/lf]
[cr/lf]
```

#### All variables 12.1

#### **Format**

VAR

- Expresses all global variables.
- When used as a readout file, all global variables currently stored are read out.
- When used as a write file, a specified global variable is written.

```
DATA FORMAT
<variable name>t = xxxxxx [cr/lf]
<variable name>t = xxxxxx [cr/lf]
<variable name>t = xxxxxx [cr/lf]
 [cr/lf]
```

Values <Variable name> ......Global variable defined in the program. Variable name is shown with 32 characters or less consisting of alphanumeric characters and underscore ("\_"). t ......Type of variable / !: real type, %: integer type, \$: character string type Integer type: integer of 8 digits or less Real type: real number of 7 digits or less including decimal fractions

Character type: character string of 255 characters or less

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

8

9

10

П

```
SAMPLE 1
SEND VAR TO CMU······Outputs all global variables
                           from communication port.
Response:
SGI0=0[cr/lf]
SGI1=1111[cr/lf]
SGI2=2222[cr/lf]
SGI3=3333 [cr/lf]
SGI4=4444[cr/lf]
SGI5=5555[cr/lf]
SGI6=6666[cr/lf]
SGI7=7777[cr/lf]
SGR0=0[cr/lf]
SGR1=1.1111E3 [cr/lf]
SGR2=2.2222E3[cr/lf]
SGR3=3.3333E3[cr/lf]
SGR4=4.4444E3[cr/lf]
SGR5=5.5555E3[cr/lf]
SGR6=6.6666E3[cr/lf]
SGR7=7.7777E3 [cr/lf]
B1%=111[cr/lf]
B2%=222[cr/lf]
C1$="CNS 1"[cr/lf]
C2$="CNS_2"[cr/lf]
[cr/lf]
```

#### SAMPLE 2

SEND CMU TO VAR..... Inputs all global variables from communication port.

#### **Format**

<variable name>t

Meaning • Expressed one variable.

#### DATA FORMAT

xxxxxx [cr/lf]



- SGIx indicates an integer type static variable.
- SGRx indicates a real type static variable.

Values <Variable name> ......Global variable defined in the program. Variable

name is shown with 32 characters or less consisting of

alphanumeric characters and underscore ("\_").

t ......Type of variable / !: real type, %: integer type, \$:

character string type

Differs depending on the type of variable:

Integer type: integer of 8 digits or less

real number of 7 digits or less including Real type:

decimal fractions

Character type: character string of 255 characters or less



 Dynamic global variables are registered during program execution. Variables cannot be referred to unless they are registered.

#### SAMPLE 1

SEND SGI6 TO CMU[cr/lf]  $\cdots$  Outputs the specified variable SGI6 from communication port.

#### Response:

6666 [cr/lf]

#### SAMPLE 2

SEND CMU TO SGI6[cr/lf]  $\cdot \cdot$  Inputs the specified variable SGI6 from communication port.

#### Response:

6666 [cr/lf] ...... Data input to the controller. OK [cr/lf] ······ Result output from the controller.

# 13 Constant file

# 13.1 One character string

#### **Format**

"<character string>"



- Expresses a specified character string.
- When used as a readout file, the specified character string is read out.
- Cannot be used as a write file.

#### DATA FORMAT

sssss...ssssss[cr/lf]

Values

 $\,\blacksquare\,$  Output of a double quotation (  $^{\shortparallel}$  ) is shown with two successive double quotations.

#### SAMPLE

Response:

"YAMAHA ROBOT"[cr/lf]

#### 14.1 All array variables

#### **Format**

ARY

- Expresses all array variables.
- When used as a readout file, all array variables are read out.
- When used as a write file, writing is performed with a specified array variable.

```
DATA FORMAT
<variable name>t(1{,m{,n}}) = xxxxxx [cr/lf]
<variable name>t(1{,m{,n}}) = xxxxxx [cr/lf]
<variable name>t(\{1, m\{, n\}\}) = xxxxxx [cr/lf]
[cr/lf]
```

#### Values

```
<Variable name> ......Global variable defined in the program. Variable
                            name is shown with 32 characters or less consisting of
                            alphanumeric characters and underscore ("_").
t .......Type of variable / !: real type, %: integer type, $: character string type
I, m, n ......Indicate array arguments.
xxxxxx ......Differs depending on the type of array variable.
                            Integer type: integer of 8 digits or less
                            Real type: real number of 7 digits or less including decimal fractions
                            Character type: character string of 255 characters or less
```

A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE 1
```

```
SEND ARY TO CMU..... Outputs all global array variables from communication port.
Response:
A!(0) = 0[cr/lf]
A!(1) = 1.E2[cr/lf]
A!(2) = 2.E2[cr/lf]
B%(0,0)=0[cr/lf]
B%(0,1)=1111[cr/lf]
B%(1,0) = 2222[cr/lf]
B%(1,1) = 3333[cr/lf]
C$(0,0,0) = "ARY1" [cr/lf]
C$(0,0,1) = "ARY2" [cr/lf]
C$(0,1,0) = "ARY3" [cr/lf]
C$(0,1,1) = "ARY4" [cr/lf]
C$(1,0,0) = "ARY5" [cr/lf]
C$(1,0,1) = "ARY6" [cr/lf]
C$(1,1,0) = "ARY7"[cr/lf]
C$(1,1,1) = "ARY8" [cr/lf]
[cr/lf]
```

#### SAMPLE 2

SEND CMU TO ARY ..... Inputs all global array variables from communication port.

# 14.2 One array variable

#### **Format**

<variable name>t(l {,m {,n }})

Meaning

Expresses one array variable.

#### DATA FORMAT

xxxxxx [cr/lf]

Values

t ......Type of variable / !: real type, %: integer type, \$: character string type

I, m, n ......Indicate array arguments.

.....

Integer type: integer of 8 digits or less

Real type: real number of 7 digits or less including

decimal fractions

Character type: character string of 255 characters or less

.....



• Array variables defined by the DIM statement are registered during compiling. Array variables cannot be referred to unless they are registered.

#### SAMPLE 1

SEND C1\$(2) TO CMU[cr/lf]  $\cdots$  Outputs the specified array variable C1\$(2) from communication port.

Response:

YAMAHA ROBOT[cr/lf]

#### SAMPLE 2

SEND CMU TO C1\$(2) [cr/lf]  $\cdots$  Inputs the specified array variable C1\$(2) from communication port.

Response:

#### **Format**

DI()

- Meaning Expresses all DI (parallel input variable) information.
  - When used as a readout file, all DI information is read out.
  - Cannot be used as a write file.

```
DATA FORMAT
DIO()=&Bnnnnnnn [cr/lf]
DI1()=&Bnnnnnnn [cr/lf]
DI27()=&Bnnnnnnn [cr/lf]
[cr/lf]
```

Values

n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., m0, reading from the left ("m" is the port No.).

A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND DI() TO CM ..... Outputs all DI information
                           from communication port.
Response:
DIO()=&B10001001[cr/lf]
DI1()=&B00000010[cr/lf]
DI2() = &B000000000[cr/lf]
DI7()=&B00000000[cr/lf]
DI10()=&B00000000[cr/lf]
DI11()=&B00000000[cr/lf]
DI12()=&B00000000[cr/lf]
DI17()=&B00000000[cr/lf]
DI20()=&B00000000[cr/lf]
DI26()=&B00000000[cr/lf]
DI27() = &B00000000[cr/lf]
[cr/lf]
```

DI file 8-31

# 15.2 One DI port

#### **Format**

DIm()

#### Meaning

- Expresses the status of one DI port.
- When used as a readout file, the specified DI port status is read out.
- Cannot be used as a write file.

## DATA FORMAT

DIm() = & Bnnnnnnnn [cr/lf]

Values

m ......0 to 7, 10 to 17, 20 to 27

n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., m0, reading from the left ("m" is the port No.).

## SAMPLE

SEND DI5() TO CMU  $\cdots\cdots$  Outputs the DI5 port status from communication port.

#### Response:

DI5()=&B00000000[cr/lf]

#### 16.1 All DO information

#### **Format**

DO()



- Expresses all DO (parallel output variable) information.
- When used as a readout file, all DO information is read out.
- Cannot be used as a write file.

```
DATA FORMAT
DO0()=&Bnnnnnnn [cr/lf]
DO1()=&Bnnnnnnn [cr/lf]
DO27()=&Bnnnnnnn [cr/lf]
[cr/lf]
```

Values

n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., m0, reading from the left ("m" is the port No.).

A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND DO() TO CMU ..... Outputs all DO information
                           from communication port.
Response:
DO0()=&B10001001[cr/lf]
DO1()=&B00000010[cr/lf]
DO2() = &B000000000[cr/lf]
DO7()=&B00000000[cr/lf]
DO10()=&B00000000[cr/lf]
DO11()=&B00000000[cr/lf]
DO12()=&B00000000[cr/lf]
DO17()=&B00000000[cr/lf]
DO20()=&B00000000[cr/lf]
DO26() = &B00000000[cr/lf]
DO27() = &B00000000[cr/lf]
[cr/lf]
```

# 16.2 One DO port

#### **Format**

DOm()



- Expresses the status of one DO port.
- When used as a readout file, the specified DO port status is read out.
- When used as a write file, the value is written to the specified DO port. However, writing to DO0() and DO1() is prohibited.
- · Readout file

#### DATA FORMAT

DOm() = & Bnnnnnnnn [cr/lf]

• Write file

#### DATA FORMAT

&Bnnnnnnn[cr/lf] or k[cr/lf]



m .......Port number: 0 to 7, 10 to 17, 20 to 27 
n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., 
m0, reading from the left ("m" is the port No.). 
k ......Integer from 0 to 255



• Writing to DO0() and DO1() is prohibited. Only referencing is permitted.

#### SAMPLE 1

SEND DO5() TO CMU······ Outputs the DO5 port status from communication port.

#### Response:

DO5()=&B00000000[cr/lf]

#### SAMPLE 2

SEND CMU TO DO5() ..... Inputs the DO5 port status from communication port.

&B00000111

#### Response:

OK[cr/lf]

17.1

#### **Format**

MO()

#### **Meaning**

- Expresses all MO (internal output variable) information.
- When used as a readout file, all MO information is read out.
- Cannot be used as a write file.

```
DATA FORMAT

MO0()=&Bnnnnnnn [cr/lf]

MO1()=&Bnnnnnnnn [cr/lf]

:

MO33()=&Bnnnnnnnn [cr/lf]

[cr/lf]
```

Values

n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., m0, reading from the left ("m" is the port No.).

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND MO() TO CMU ..... Outputs all MO information
                             from communication port.
Response:
MOO() = &B10001001[cr/lf]
MO1() = &B00000010[cr/lf]
MO2() = &B000000000[cr/lf]
MO7()=&B00000000[cr/lf]
MO10() = \&B000000000[cr/lf]
MO11() = &B000000000[cr/lf]
MO12() = &B000000000[cr/lf]
MO17()=&B00000000[cr/lf]
MO20() = &B00000000[cr/lf]
MO32() = \&B000000000[cr/lf]
MO33() = &B00000000[cr/lf]
[cr/lf]
```

MO file 8-35

U

10

11

# 17.2 One MO port

#### **Format**

MOm ()



- Expresses the status of one MO port.
- When used as a readout file, the specified MO port status is read out.
- When used as a write file, the value is written to the specified MO port. However, writing to MO30() to MO37() is prohibited.
- · Readout file

#### DATA FORMAT

MOm() = & Bnnnnnnnn [cr/lf]

• Write file

#### DATA FORMAT

&Bnnnnnnn[cr/lf] or k[cr/lf]





• Writing to MO30() to MO37() is prohibited. Only reference is permitted.

#### SAMPLE 1

SEND MO5() TO CMU······ Outputs the MO5 port status from communication port.

#### Response:

MO5() = &B000000000[cr/lf]

#### SAMPLE 2

SEND CMU TO MO5() ..... Inputs the MO5 port status from communication port.

&B00000111

#### Response:

OK[cr/lf]

## Format

LO()

#### Meaning

- Expresses all LO (internal output variable) information.
- When used as a readout file, all LO information is read out.
- Cannot be used as a write file.

#### DATA FOMAT

LO0()=&Bnnnnnnn [cr/lf] LO1()=&Bnnnnnnn [cr/lf]

[cr/lf]

Values

n ......"0" or "1" (total of 8 digits). Corresponds to 07, 06, ..., 00, reading from the left.

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

#### SAMPLE

SEND LO() TO CMU  $\cdots\cdots\cdots$  Outputs all LO status from communication port.

#### Response:

LOO() = &B10001001[cr/lf]

LO1()=&B00100100[cr/lf]

[cr/lf]

9

10

11

# 18.2 One LO port

#### **Format**

LOm()



- Expresses the status of one LO port.
- When used as a readout file, the specified LO port status is read out.
- When used as a write file, the value is written to the specified LO port.
- · Readout file

## DATA FORMAT

LOm()=&Bnnnnnnnn[cr/lf]

• Write file

#### DATA FORMAT

&Bnnnnnnn[cr/lf] or k[cr/lf]

Values

#### SAMPLE 1

SEND LO0() TO CMU  $\cdots\cdots$  Outputs the LO0 port status from communication port.

#### Response:

LOO()=&B00000000[cr/lf]

#### SAMPLE 2

SEND CMU TO LO0() ...... Inputs the LO0 port status from communication port.

&B00000111

#### Response:

OK[cr/lf]

#### **All TO information** 19.1

#### **Format**

TO()



- Expresses all TO (timer output variable) information.
- When used as a readout file, all TO information is read out.
- Cannot be used as a write file.

#### DATA FORMAT

TOO()=&Bnnnnnnn [cr/lf] TO1()=&Bnnnnnnn [cr/lf] [cr/lf]

Values

n ......"0" or "1" (total of 8 digits). Corresponds to 07, 06, ..., 00, reading from the left ("m" is the port No.).

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

#### SAMPLE

SEND TO() TO CMU ······ Outputs all TO status from communication port.

#### Response:

TO0()=&B10001001[cr/lf] TO1()=&B10001001[cr/lf] [cr/lf]

# 19.2 One TO port

#### **Format**

TOm()



- Expresses the status of one TO port.
- When used as a readout file, the specified TO port status is read out.
- When used as a write file, the value is written to the specified TO port.
- · Readout file

## DATA FORMAT

TOm() = & Bnnnnnnnn [cr/lf]

• Write file

#### DATA FORMAT

&Bnnnnnnn[cr/lf] or k[cr/lf]

Values

#### SAMPLE 1

SEND TO0() TO CMU  $\cdots\cdots$  Outputs the TO0 port status from communication port.

#### Response:

TO0()=&B00000000[cr/lf]

## SAMPLE 2

SEND CMU TO TOO() ...... Inputs the TOO port status from communication port.

&B00000111

#### Response:

OK[cr/lf]

## 20.1 All SI information

#### **Format**

SI()

#### Meaning

- Expresses all SI (serial input variable) information.
- When used as a readout file, all SI information is read out.
- Cannot be used as a write file.

```
DATA FORMAT

SIO()=&Bnnnnnnn [cr/lf]

SI1()=&Bnnnnnnn [cr/lf]

:

SI27()=&Bnnnnnnnn [cr/lf]

[cr/lf]
```

Values

n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., m0, reading from the left ("m" is the port No.).

A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND SI() TO CMU ..... Outputs all SI status from
                            communication port.
Response:
SIO()=&B10001001[cr/lf]
SI1()=&B00000010[cr/lf]
SI2() = \&B000000000[cr/lf]
SI7() = &B000000000[cr/lf]
SI10()=&B00000000[cr/lf]
SI11()=&B00000000[cr/lf]
SI12()=&B00000000[cr/lf]
SI17()=&B00000000[cr/lf]
SI20() = &B000000000[cr/lf]
SI26() = \&B000000000[cr/lf]
SI27() = &B000000000[cr/lf]
[cr/lf]
```

# 20.2 One SI port

#### **Format**

SIm()

## Meaning

- Expresses the status of one SI port.
- When used as a readout file, the specified SI port status is read out.
- Cannot be used as a write file.

## DATA FORMAT

SIm()=&Bnnnnnnnn[cr/lf]



## SAMPLE

SEND SI5() TO CMU  $\cdots\cdots$  Outputs the SI5 port status from communication port.

#### Response:

SI5()=&B00000000[cr/lf]

# 8

# 21.1 All SO information

#### **Format**

SO()

#### Meaning

- Expresses all SO (serial output variable) information.
- When used as a readout file, all SO information is read out.
- Cannot be used as a write file.

```
DATA FORMAT

SO0()=&Bnnnnnnn [cr/lf]

SO1()=&Bnnnnnnn [cr/lf]

:

SO27()=&Bnnnnnnnn [cr/lf]

[cr/lf]
```

Values

n ......"0" or "1" (total of 8 digits). Corresponds to m7, m6, ..., m0, reading from the left ("m" is the port No.).

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND SO() TO CMU ..... Outputs all SO status from
                            communication port.
Response:
SO0()=&B10001001[cr/lf]
SO1()=&B00000010[cr/lf]
SO2() = \&B000000000[cr/lf]
SO7() = &B000000000[cr/lf]
SO10()=&B00000000[cr/lf]
SO11()=&B00000000[cr/lf]
SO12()=&B00000000[cr/lf]
SO17()=&B00000000[cr/lf]
SO20() = &B000000000[cr/lf]
SO26() = \&B000000000[cr/lf]
SO27() = &B000000000[cr/lf]
[cr/lf]
```

SO file 8-43

U

10

11

# 21.2 One SO port

#### **Format**

SOm()



- Expresses the status of one SO port.
- When used as a readout file, the specified SO port status is read out.
- When used as a write file, the value is written to the specified SO port. However, writing to SO0() and SO1() is prohibited.
- · Readout file

#### DATA FORMAT

SOm() = &Bnnnnnnnn [cr/lf]

• Write file

#### DATA FORMAT

&Bnnnnnnnn[cr/lf] or k[cr/lf]





• Writing to SO0() and SO1() is prohibited. Only reference is permitted.

#### SAMPLE 1

SEND SO5() TO CMU·········· Outputs the SO5 port status from communication port.

#### Response:

SO5()=&B00000000[cr/lf]

#### SAMPLE 2

SEND CMU TO SO5() ..... Inputs the SO5 port status from communication port.

&B00000111

#### Response:

OK[cr/lf]

22

#### 22.1 **EOF** data

#### **Format**

EOF



- Meaning This file is a special file consisting only of a ^Z (=1Ah) code. When transmitting data to an external device through the communication port, the EOF data can be used to add a ^Z code at the end of file.
  - When used as a readout file,  $^{Z}$  (=1Ah) is read out.
  - Cannot be used as a write file.

## DATA FORMAT

^Z (=1Ah)

```
SAMPLE
```

```
SEND PGM TO CMU
SEND EOF TO CMU·····Outputs
                                    EOF
                                          data
                                                 from
                         communication port.
NAME=TEST1[cr/lf]
A=1[cr/lf]
HALT[cr/lf]
[cr/lf]
^Z
```



• A "^Z" code may be required at the end of the transmitted file, depending on the specifications of the receiving device and application.

# 23 Serial port communication file

# 23.1 Serial port communication file

## **Format**

CMU

#### Meaning

- Expresses the serial communication port.
- Depends on the various data formats.

#### SAMPLE

SEND PNT TO CMU··········Outputs all point data from communication port.

SEND CMU TO PNT ·······Inputs all point data from

communication port.

#### 24.1 **All SIW**

## **Format**

SIW()

- Meaning Expresses all SIW (serial word input) data.
  - Reads out all SIW information in hexadecimal digit when used as a readout file.
  - Cannot be used as a write file.

```
DATA FORMAT
SIW(0)=&Hnnnn [cr/lf]
SIW(1)=&Hnnnn [cr/lf]
SIW(15) = & Hnnnn [cr/lf]
[cr/lf]
```

Values

n .......0 to 9, A to F: 4 digits (hexadecimal)

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND SIW() TO CMU······Outputs all SIW data from
                           communication port.
Response:
SIW(0) = &H1001[cr/lf]
SIW(1) = &H0010[cr/lf]
SIW(2) = &H0000[cr/lf]
SIW(15) = &H0000[cr/lf]
[cr/lf]
```

# 24.2 One SIW data

#### **Format**

SIW (m)

#### Meaning

- Expresses one SIW status.
- Reads out all SIW information in hexadecimal digit when used as a readout file.
- Cannot be used as a write file.

## DATA FORMAT

SIW(m)=&Hnnnn [cr/lf]

Values

m ......0 to 15

n .......0 to 9, A to F: 4 digits (hexadecimal)

#### SAMPLE

SEND SIW(5) TO CMU ..... Outputs SIW(5) from communication port.

#### Response:

SIW(5) = &H1001[cr/lf]

## **Format**

SOW()

- Meaning Expresses all SOW (serial word output) data.
  - Reads out all SOW information in hexadecimal digit when used as a readout file.
  - Cannot be used as a write file.

```
DATA FORMAT
SOW(0)=&Hnnnn [cr/lf]
SOW(1)=&Hnnnn [cr/lf]
SOW(15) = & Hnnnn [cr/lf]
[cr/lf]
```

Values

n .......0 to 9, A to F: 4 digits (hexadecimal)

• A line containing only [cr/lf] is added at the end of the file, indicating the end of the file.

```
SAMPLE
SEND SOW() TO CMU······Outputs all SOW data from
                           communication port.
Response:
SOW(0) = &H1001[cr/lf]
SOW(1) = &H0010[cr/lf]
SOW(2) = &H0000[cr/lf]
SOW(15) = &H0000[cr/lf]
[cr/lf]
```

SOW file 8-49

# 25.2 One SOW data

#### **Format**

SOW (m)



- Expresses one SOW status.
- When used as a readout file, the specified SOW port status is read out.
- When used as a write file, the value is written to the specified SOW. However, writing to SOW0() and SOW1() is prohibited.
- Readout file

#### DATA FORMAT

SOW(m)=&Hnnnn [cr/lf]

• Write file

#### DATA FORMAT

&Hnnnn



m ......2 to 15

n .......0 to 9, A to F: 4 digits (hexadecimal)

#### SAMPLE 1

SEND SOW(5) TO CMU ········Outputs SOW(5) from communication port.

Response:

SOW(5) = &H1001[cr/lf]

## SAMPLE 2

SEND CMU TO SOW(5) ...... Input to SOW(5) from communication port.

&H1001

Response:

OK[cr/lf]

#### Ethernet port communication file 26.1

## **Format**

26

ETH



- Expresses the Ethernet port.
- Depends on the various data formats.

## SAMPLE

SEND PNT TO ETH......Outputs all point data from the Ethernet port. SEND ETH TO PNT..... Inputs all point data from the Ethernet port.

# Chapter 9 User program examples

1	Basic operation9-1
2	Application9-8


# 1.1 Directly writing point data in program

#### Overview

**Basic operation** 

The robot arm can be moved by PTP (point-to-point) motion by directly specifying point data in the program.

**Processing flow** 



33C01-R7-00

SAMPLE						
MOVE P,	300.00	300.00	50.00	90.00	0.00	0.00
MOVE P,	300.00	100.00	0.00	0.00	0.00	0.00
MOVE P,	200.00	200.00	10.00	-90.00	0.00	0.00
HALT						


# 1.2 Using point numbers

#### Overview

Coordinate data can be specified by using point numbers in a program. Coordinate data should be entered beforehand in "MANUAL>POINT" mode, for example as shown below.

POINT	DATA						
P0=	0.00	0.00	0.00	0.00	0.00	0.00	
P1=	100.00	0.00	150.00	30.00	0.00	0.00	
P2=	0.00	100.00	50.00	0.00	0.00	0.00	
P3=	300.00	300.00	0.00	0.00	0.00	0.00	
P4=	300.00	100.00	100.00	90.00	0.00	0.00	
P5=	200.00	200.00	0.00	0.00	0.00	0.00	

## **Processing flow**



33C02-R7-00

```
MOVE P,P0
MOVE P,P1
MOVE P,P2
MOVE P,P3
MOVE P,P4
MOVE P,P5
HALT
```

```
FOR J=0 TO 5

MOVE P,P[J]

NEXT J

HALT
```

Although the same operation is executed by both SAMPLE 1 and SAMPLE 2, the program can be shortened by using point Nos. and the FOR statement.


# Using shift coordinates

#### Overview

In the example shown below, after PTP movement from P3 to P5, the coordinate system is shifted +140mm along the X-axis and -100mm along the Y-axis, and the robot then moves from P3 to P5 again. The shift coordinate data is set in S1 and P3, P4, P5 are set as described in the previous section ("1.2 Using point numbers").

SHIFT	DATA				
S0=	0.00	0.00	0.00	0.00	
S1=	140.00 -	100.00	0.00	0.00	

#### **Shift Coordinate**



33C03-R7-00

```
SAMPLE

SHIFT S0 Shift 0.

FOR J=3 TO 5 Repeated movement from P3 to P5.

MOVE P, P[J]

NEXT J

SHIFT S1 Changed to "shift 1".

FOR K=3 TO 5 Repeated movement occurs in the same manner from P3 to P5.

MOVE P,P[K]

NEXT K
```

O

10

11

# 1.4 Palletizing

## 1.4.1 Calculating point coordinates


#### Overview

Repetitive movement between a fixed work supply position P0 and each of the equally spaced points on a pallet can be performed with the following program.

In the drawing below, points N1 to N20 are on Cartesian coordinates, consisting of 5 points positioned at a 50mm pitch in the X-axis direction and 4 points at a 25mm pitch in the Y-axis direction. The robot arm moves from point to point in the order of P0-N1-P0-N2...N5-P0-N6-P0... while repeatedly moving back and forth between point P0 and each pallet.


POINT DATA								
Work supply position:								
P0=	0.0	0.0	0.0	0.0	0.0	0.0		
X-axis p	itch:							
P10=	50.0	0.0	0.0	0.0	0.0	0.0		
Y-axis p	itch:							
P20=	0.0	25.0	0.0	0.0	0.0	0.0		
N1 position:								
P1 =	100.0	50.0	0.0	0.0	0.0	0.0		

#### Calculating point coordinates



33C04-R7-00

#### **Processing flow**



31C05-R7-00

```
P100=P1
P200=P1
FOR J=1 TO 4
FOR K=1 TO 5
MOVE P, P0
MOVE P, P100
P100=P100+P10
NEXT K
P200=P200+P20
P100=P200
NEXT J
```


# 1.4.2 Utilizing pallet movement

#### Overview

Repetitive movement between a fixed work supply position P0 and each of the equally spaced points on a pallet can be performed with the following program. In the drawing below, points N1 to N24 are on Cartesian coordinates, consisting of 3 points positioned at a 50mm pitch in the X-axis direction, 4 points at a 50mm pitch in the Y-axis direction, and 2 points at 100mm pitch in the Z-axis direction. The robot arm moves from point to point in the order of P0-N1-P0-N2...-N5-P0-N6... while repeatedly moving back and forth between point P0 and each pallet.


POINT DA	ГА					
Work sup	ply posi	tion:				
P0=	0.00	0.00	100.00	0.00	0.00	0.00
Pallet d	efinition	:				
PL0						
NX = 3						
NY= 4						
NZ = 2						
PLP= 399	6 (P3996	to P400	00 are us	ed)		
P3996=	100.00	50.00	100.00	0.00	0.00	0.00
P3997=	200.00	50.00	100.00	0.00	0.00	0.00
P3998=	100.00	200.00	100.00	0.00	0.00	0.00
P3999=	200.00	200.00	100.00	0.00	0.00	0.00
P4000=	100.00	50.00	200.00	0.00	0.00	0.00

# **Utilizing pallet movement**



33C06-R7-00

#### **Processing flow**



33C07-R7-00

```
FOR I=1 TO 24 ······ Repeated for I = 1 to 24.

MOVE P,P0,Z=0.00 ····· Movement to supply position.

PMOVE (0,I),Z=0.00 ···· Movement to pallet point.


NEXT I

MOVE P,P0,Z=0.00
```

#### Overview

The following example shows general-purpose signal input and output operations through the STD.

# Processing flow



33C08-R7-00

```
SAMPLE
WAIT DI2( )=0 ····· Wait until DI20 to DI27 become "0".
DELAY 1000
WAIT DI2(0)=1 ...... Wait until DI21 becomes "1".
N=1
*LOOP1:
IF DI2(1)=1 THEN *PROGEND ··· Jumps to *PROGEND if DI21 = 1.
IF N>20 THEN *ALLEND ...... Ended in N > 20 (jumps to *ALLEND).
DELAY 500
N=N+1
GOTO *LOOP1 ..... Loop is repeated.
' END ROUTINE
*PROGEND: .... End processing.
DO2(7,6,1,0)=&B1111..... Set DO27, 26, 21, 20 to "1".
DELAY 2000 ····· Wait 2 seconds
DO2()=0 ...... Set DO20 to "0".
*ALLEND:
HALT
```


# 2 Application

# 2.1 Pick and place between 2 points

#### Overview

The following is an example for picking up a part at point A and placing it at point B.

# Pick and place between 2 points



33C09-R7-00

#### Precondition

- 1. Set the robot movement path.
  - Movement path:  $P3 \rightarrow P1 \rightarrow P3 \rightarrow P4 \rightarrow P2 \rightarrow P4$
  - Locate P3 and P4 respectively at a position 50mm above P1 and P2 and set the P1 and P2 positions by teaching.

#### 2. I/O signal

DO (20) Chuck (gripper) open/close = 0: open, 1: close

• A 0.1 second wait time is set during chuck open and close.

```
SAMPLE: When calculating to find P3 and P4
   P4=P2 ····· P2 coordinates are assigned to P4.
  LOC3(P3)=LOC3(P3)-50.0···· P3 is shifted 50mm in Z UP direction.
  LOC3(P4)=LOC3(P4)-50.0···· P4 is shifted 50mm in Z UP direction.
  MOVE P, P3
  GOSUB *OPEN
  MOVE P, P1
  GOSUB *CLOSE
  MOVE P, P3
  MOVE P, P4
  MOVE P, P2
  GOSUB *OPEN
  MOVE P, P4
  HALT
*OPEN:
            ..... Chuck OPEN routine.
  DO2(0) = 0
  DELAY 100
  RETURN
*CLOSE: ..... Chuck CLOSE routine.
  DO2(0)=1
  DELAY 100
   RETURN
```

11


```
SAMPLE: When using arch motion
  P4=P2 ····· P2 coordinates are assigned to P4.
  LOC3(P4) = LOC3(P4) - 50.0 \cdots The axis 3 data of P4 is
                         shifted by 50mm.
  GOSUB *OPEN
  MOVE P,P1,A3=30.0 \cdots Arch motion at A3 = 30mm.
  GOSUB *CLOSE
  MOVE P, P2, A3=30.0 \cdots Arch motion at A3 = 30mm.
  GOSUB *OPEN
  MOVE P,P4
  HALT
*OPEN: ..... Chuck OPEN routine.
  DO2(0) = 0
  DELAY 100
  RETURN
*CLOSE: ..... Chuck CLOSE routine.
  DO2(0)=1
  DELAY 100
  RETURN
```

#### **Palletizing** 2.2

# Overview

The following is an example for picking up parts supplied from the parts feeder and placing them on a pallet on the conveyor. The pallet is ejected when full.

# **Palletizing**



33C10-R7-00

# Precondition

# I/O signal

DI (30)	Component detection sensor	1: Parts are supplied
DI (31)	Pallet sensor	1: Pallet is loaded

DO (30)	Robot hand open/close	0: Open / 1: Close
DO (31)	Pallet eject	1: Eject

Robot hand open/close time is 0.1 second and pallet eject time is 0.5 seconds.

The points below should be input beforehand as point data.

P0	Part supply position
P1	Pallet reference position
P10	X direction pitch
P11	Y direction pitch

Vertical movement is performed to a position Z=50mm above the pallet and parts feeder.

```
SAMPLE 1: When point is calculated
WHILE -1 ..... All repeated (-1 is always TRUE).
FOR A=0 TO 2
FOR B=0 TO 2
   WAIT DI(31)=1 ..... Wait until a pallet "present"
                         status occurs.
  WAIT DI(30)=1 ····· Wait until the supplied component
                         "present" status occurs.
  DO(30) = 0 \cdots Robot hand OPENS.
  DELAY 100
  MOVE P, P0, A3=50.0 ······ Movement to supply position.
  DO(30) = 1 \cdot \cdot \cdot \cdot \cdot Robot hand CLOSES.
  DELAY 100
  P100=P1+P10*B+P11*A····· Next point is calculated.
  MOVE P, P100, A3=50.0 ····· Movement to calculated point.
  DO(30) = 0 \cdots Robot hand OPENS.
  DELAY 100
NEXT
NEXT
DRIVE (3,0) .....Only Z-axis moves to 0.
DO(31)=1 ····· Pallet is ejected.
DELAY 500
DO(31) = 0
WEND
       .....Loop is repeated.
HALT
```

```
SAMPLE 2: When using the palletizing function
* Precondition: Must be defined at pallet "0".
WHILE -1 ..... All repeated.
FOR A=1 TO 9
   WAIT DI(31)=1 ..... Wait until a pallet "present"
                         status occurs.
   WAIT DI(30)=1 ····· Wait until the supplied component
                         "present" status occurs.
   DO(30) = 0 \cdots Robot hand OPENS.
   DELAY 100
   MOVE P, P0, A3=50.0 ······· Movement to supply position.
   DO(30)=1·····Robot hand CLOSES.
   DELAY 100
   PMOVE(0,A), A3=50.0 ...... Movement to pallet point.
   DO(30) = 0 \cdots Robot hand OPENS.
   DELAY 100
DRIVE(3,0) .....Only Z-axis moves to 0.
DO(31)=1 Pallet is ejected.
DELAY 500
DO(31) = 0
WEND
        ..... Loop is repeated.
HALT
```

#### Pick and place of stacked parts 2.3


#### Overview

The following is an example for picking up parts stacked in a maximum of 6 layers and 3 blocks and placing them on the conveyor.

The number of parts per block may differ from others.

Parts are detected with a sensor installed on the robot hand.

# Pick and place of stacked parts



33C11-R7-00

# Precondition

# I/O signal


DI (30)	Component detection sensor	1: Parts are supplied
DI (31)	Robot hand open/close	0: Open / 1: Close

- Robot hand open/close time is 0.1 seconds.
- The points below should be input beforehand as point data.

P1	Bottom of block 1
P2	Bottom of block 2
P3	Bottom of block 3
P5	Position on conveyor

Movement proceeds at maximum speeds but slows down when in proximity to the part.

# **Processing flow**



33C12-R7-00

Use a STOPON condition in the MOVE statement for sensor detection during movement.

```
SAMPLE
FOR A=1 TO 3
SPEED 100
GOSUB *OPEN
P6=P[A]
LOC3(P6) = 0.00
MOVE P, P6, A3=0.0
WHILE -1
  SPEED 20
   MOVE P, P[A], STOPON DI3(0)=1
   IF DI3(0)=0 THEN *L1
   ' SENSOR ON
  P4=JTOXY(WHERE)
   GOSUB *CLOSE
   SPEED 100
   MOVE P, P5, A3=0.0
   GOSUB *OPEN
   MOVE P, P4, A3=0.0
WEND
*L1: 'SENSOR OFF
NEXT A
SPEED 100
DRIVE (3,0)
HALT
*OPEN:
DO3(0) = 0
DELAY 100
RETURN
*CLOSE:
DO3(0)=1
DELAY 100
RETURN
```

#### 2.4 Parts inspection (Multi-tasking example)

#### Overview

One robot is used to inspect two different parts and sort them according to the OK/NG results.


The robot picks up the part at point A and moves it to the testing device at point B. The testing device checks the part and sends it to point C if OK or to point D if NG.

The part at point A' is picked up and moved to the testing device at point B' in the same way. The testing device checks the part and sends it to point C' if OK or to point D' if NG.

It is assumed that 10 to 15 seconds are required for the testing device to issue the OK/NG results.

# Parts inspection (Multi-tasking example)

7 6 5 4 3 2 1 0



33C13-R7-00



\*1: As the start signal, supply a 0.1 second pulse signal to the testing device.




- \*2: Chuck open and close time is 0.1 seconds.
- \*3: Each time a test is finished, the test completion signal and OK/NG signal are sent from the testing device. After testing, the test completion signal turns ON (=1), and the OK/NGsignal turns ON (=1) when the result is OK and turns OFF (=0) when NG.

#### Precondition

I/O signal

I/O signal



33C14-R7-00


- 2. The main task (task 1) is used to test part 1 and the subtask (task 2) is used to test part 2.
- An exclusive control flag is used to allow other tasks to run while waiting for the test completion signal from the testing device.

FLAG1	0: Executing Task 1	(Task 2 execution enabled)
	1: Task 1 standby	(Task 2 execution disabled)
FLAG2	0: Executing Task 2	(Task 1 execution enabled)
	1: Task 2 standby	(Task 1 execution disabled)

Ц

# Processing flow

4. Flow chart



Task 2 (subtask) runs in the same flow.

# ■ Program example

SAMPLE		
<main task=""> FLAG1=0 FLAG2=0 UPPOS=0.0 START <sub pgm="">,T2</sub></main>	Subtask Start	<subtask></subtask>
*L1: WAIT DI2(2)=1 WAIT FLAG2=0 FLAG1=1 GOSUB *OPEN MOVE P,P1,Z=UPPOS GOSUB *CLOSE MOVE P,P2,Z=UPPOS GOSUB *OPEN DRIVEI (3,-10000)	Part supply standby Other tasks waiting for standby status. Exclusive control flag set Chuck open Move to part supply position Chuck close Move to testing device Chuck open Move Z-axis upward Z 10,000 pulses	WAIT DI3(2)=1 WAIT FLAG1=0 FLAG2=1 GOSUB *OPEN MOVE P,P11,Z=UPPOS GOSUB *CLOSE MOVE P,P12,Z=UPPOS GOSUB *OPEN
FLAG1=0 DO2(0)=1 DELAY 100 DO2(0)=0 WAIT DI2(0)=1	Exclusive control flag reset Testing device start Test completion standby	FLAG2=0 DO3(0)=1 DELAY 100
WAIT DI2(0)=1 WAIT FLAG2=0 FLAG1=1 MOVE P,P2,Z=UPPOS GOSUB *CLOSE IF DI2(1)=1 THEN 'GOOD	Task completion standby Exclusive control flag set	WAIT DI3(0)=1 WAIT FLAG1=0
WAIT DI4(2)=0 MOVE P,P3,Z=UPPOS ELSE 'NG		'GOOD WAIT DI3(3)=0 MOVE P,P13,Z=UPPOS ELSE
	Part movement standby Move to NG parts position Chuck open	'NG WAIT DI3(4)=0 MOVE P,P14,Z=UPPOS ENDIF
DRIVEI (3,-10000) FLAG1=0 GOTO *L1 *OPEN: DO2(1)=0 DELAY 100 RETURN *CLOSE: DO2(1)=1 DELAY 100 RETURN	Move Z-axis upward Z 10,000 pulses Exclusive control flag reset	

#### Connection to an external device through RS-232C (example 1) 2.5

#### Overview

Point data can be written in a program by using an external device connected to the RCX340 series controller via the RS-232C port.

#### Precondition

1. Input to the external device from the controller SDATA/X/Y [cr/lf]

2. Output to the controller from the external device

# (cr/lf) indicates CR code (=0Dh) + LF code (=0Ah).

POINT	DATA						
P10=	156.42	243.91	0.00	0.00	0.00	0.00	[cr/lf]

```
SAMPLE
' INIT
   VCMD$="SDATA/X/Y"
   P0= 0.00
                0.00
                        0.00
                                0.00
                                        0.00
                                                0.00
' MAIN ROUTINE
   MOVE P, P0
*ST:
   SEND VCMD$ TO CMU
   SEND CMU TO P10
   MOVE P, P10
GOTO *ST
```



- "SEND xxx TO CMU" outputs the contents specified by "xxx" through the RS-232C.
- "SEND CMU TO xxx" sends data into the files specified by "xxx" through the RS-232C.


#### Connection to an external device through RS-232C (example 2) 2.6

#### Overview

Point data can be created from the desired character strings and written in a program by using an external device connected to the RCX340 controller via the RS-232C port.

#### Precondition

1. Input to the external device from the controller SDATA/X/Y [cr/lf]





(cr/lf) indicates CR code

(=0Dh) + LF code (=0Ah).

- "SEND xxx TO CMU" outputs the contents specified by "xxx" through the RS-232C.
- "SEND CMU TO xxx" sends data into the files specified by "xxx" through the RS-232C.
- The LEN () function obtains the length of the character string.
- The MID\$ () function obtains the specified character string from among the character strings.
- The VAL () function obtains the value from the character string.

П

```
SAMPLE
'INT
  VCMD$="SDATA/X/Y"
  VIN$=""
  VX$=""
  VY$=""
                                0.00
         0.00 0.00 0.00
  P0 =
                                          0.00
                                                   0.00
  P11= 100.00 100.00 0.00
                                   0.00
                                           0.00
                                                   0.00
' MAIN ROUTINE
  MOVE P, PO
*ST:
   SEND VCMD$ TO CMU
   SEND CMU TO VIN$
   I=1
  VMAX=LEN(VIN$)
*LOOP:
  IF I>VMAX THEN GOTO *E LOOP
   C$=MID$(VIN$,I,1)
   IF C$="X" THEN
     I=I+2
     J=I
*X LOOP:
     C$=MID$(VIN$, J, 1)
     IF C$="," THEN
*X1 LP:
        L=J-I
        VX$=MID$(VIN$, I, L)
        I=J+1
        GOTO *LOOP
     ENDIF
     J=J+1
     IF J>VMAX THEN GOTO *X1 LP
     GOTO *X_LOOP
   ENDIF
   IF C$="Y" THEN
     I=I+2
     J=I
*Y LOOP:
     C$=MID$(VIN$, J, 1)
     IF C$=","THEN
*Y1 LP:
        L=J-I
        VY$=MID$(VIN$, I, L)
        I=J+1
        GOTO *LOOP
     ENDIF
     J=J+1
     IF J>VMAX THEN GOTO *Y1 LP
     GOTO *Y_LOOP
   END IF
   I = I + 1
   GOTO *LOOP
*E LOOP:
   WX=VAL(VX$)
   WY=VAL(VY$)
  LOC1(P11) = WX
   LOC2(P11) = WY
   MOVE P, P11
GOTO *ST
```

# Chapter 10 Online commands

1	Online Command List10-1
2	Operation and setting commands 10-6
3	Reference commands10-14
4	Operation commands 10-24
5	Data file operation commands10-28
6	Utility commands10-39
7	Executing the robot language independently 10-41
8	<b>Control codes</b> 10-42

10

# **Online Command List**

Online commands can be used to operate the controller via an RS-232C interface or via an Ethernet. This chapter explains the online commands which can be used. For details regarding the RS-232C and Ethernet connection methods, refer to the "RCX340 Controller User's Manual".

# About termination codes

During data transmission, the controller adds the following codes to the end of a line of transmission data.

- RS-232C
  - CR (0Dh) and LF (0Ah) are added to the end of the line when the "Termination code" parameter of communication parameters is set to "CRLF".
  - CR (0Dh) is added to the end of the line when the "Termination code" parameter of communication parameters is set to "CR".
- Ethernet
  - CR (0Dh) and LF (0Ah) are added to the end of the line.

When data is received, then the data up to CR (0Dh) is treated as one line regardless of the "Termination code" parameter setting, so LF (0Ah) is ignored.

The termination code is expressed as [cr/lf] in the detailed description of each online command stated in "2 Operation and setting commands" onwards in this chapter.

# 1.1 Online command list: Function specific

# Key operation

Operation type		Command	Option
Change mode	AUTO mode	AUTO	
	MANUAL mode	MANUAL	
Program	Reset program	RESET	
	Execute program	RUN	
	Execute one line	STEP	
	Skip one line	SKIP	
	Execute to next line	NEXT	
	Stop program	STOP	
Set break point		BREAK	m, n (m: break point No., n: line)
Change manual speed		MSPEED	k (k : 1-100)
Move to absolute reset position		ABSADJ	k, 0 or k, 1 (k : 1-6)
Return-to-origin		ORGRTN	k (k : 1-6)
Manual movement (inching)		INCH	k+ or k- (k : X, Y, Z, R, A, B)
Manual movement (jog)		JOG	k+ or k- (k : X, Y, Z, R, A, B)
Point data teaching		TEACH	m (m : point No.)

# Utility

	Operation type	Command	Option
Copy program 1 to program 2		COPY	<pre><pre><pre><pre>cprogram 1&gt; TO <pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre>
Copy points "m - n" to point "k"			Pm-Pn TO Pk
	ments "m - n" to point comment "k"		PCm-PCn TO PCk
Delete progran	n	ERA	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>
Delete points "	m - n"		Pm-Pn
Delete point co	omments "m - n"		PCm-PCn
Delete pallet "r	n"		PLm
Rename "prog	ram 1" to "program 2"	REN	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>
Change progra	am attribute	ATTR	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>
Initialize data	Program	INIT	PGM
	Point		PNT
	Shift		SFT
	Hand		HND
	Pallet		PLT
	Point comment		PCM
	All data except parameters		MEM
	Parameter		PRM
	All data (MEM+PRM)		ALL
Initialize data	Communication parameter	INIT	CMU
Initialize data	Error log	INIT	LOG
Setting Setting Access level		ACCESS	k
Sequence execution flag		SEQUENCE	k
Check or set date		DATE	
Check or set time		TIME	

- Conditions: 1. Always executable.
  - 2. Not executable during inputs from the programming box.
  - 3. Not executable during inputs from the programming box, and while the program is
  - 4. Not executable during inputs from the programming box, while the program is running, and when specific restrictions apply.

# Data handling

Operation type	Command	Option	Condition
Acquiring status Access level	?	ACCESS	1
Arm status		ARM	
Break point status		BREAK	
Mode indication		MOD	
Return-to-origin status		ORIGIN	
Servo status		SERVO	
Sequence execution flag status		SEQUENCE	
Version information		VER	
Current robot position (pulse coordinate)		WHERE	
Current robot position (XY coordinate)		WHRXY	
Task number		TASKS	
Task operation status		TSKMON	
Selected shift status		SHIFT	
Selected hand status		HAND	
Remaining memory capacity		MEM	
Emergency stop status		EMG	
Numerical data		Numerical expression	
Character string data		Character string expression	
Point data		Point expression	
Shift data		Shift expression	
Data readout	READ		2
Data write	WRITE		2

# ■ Robot language independent execution

Operation type	Command	Option	Condition
Robot language executable independently			4

# Control code

Operation type	Command	Option	Condition
Execution language interruption	^C(=03H)		1

Conditions: 1. Always executable.

- 2. Not executable during inputs from the programming box.
- 3. Not executable during inputs from the programming box, and while the program is running.
- 4. Not executable during inputs from the programming box, while the program is running, and when specific restrictions apply.

# 1.2 Online command list: In alphabetic order

Command	Option	Meaning	Condition
?	ACCESS	Acquire access level	1
	ARM	Acquire arm status	1
	BREAK	Acquire break point status	1
	CONFIG	Acquire controller configuration	1
	EMG	Acquire emergency stop status	1
	EXELVL	Acquire execution level	1
	HAND	Acquire selected hand status	1
	MEM	Acquire remaining memory capacity	1
	MOD	Acquire mode indication	1
	MSG [m, n]	Acquire error message	1
	OPSLOT	Acquire option slot status	1
	ORIGIN	Acquire return-to-origin status	1
	SELFCHK	Acquire error status by self-diagnosis	1
	SEQUENCE	Acquire sequence execution flag status	1
	SERVO	Acquire servo status	1
	SHIFT	Acquire selected shift status	1
	MSPEED	Acquire MANUAL speed status	1
	TASKS	Acquire task number	1
	TSKMON	Acquire task operation status	1
	VER	Acquire version	1
	WHERE	Acquire current robot position (pulse coordinate)	1
	WHRXY	Acquire current robot position (XY coordinate)	1
	WHRXYEX	Acquire current robot position (XY coordinate)	1
	Shift expression	Acquire shift data	1
	Point expression	Acquire point data	1
	Numeric expression	Acquire numeric data	1
	Character string expression	Acquire character string data	1
^C (=03H)		Execution language interruption	1
ABSADJ	k, 0 or k, 1 (k : 1-6)	Move to absolute reset position	3
ACCESS	k	Set access level	3
ATTR	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Change program attribute	3
AUTO		Change mode: AUTO mode	3
BREAK	m, n (m: break point No., n: line)	Set break point	4
COPY	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Copy program 1 to program 2	3
001 1	PCm-PCn TO PCk	Copy point comments "m - n" to point comments "k"	3
	Pm-Pn TO Pk	Copy points "m - n" to points "k"	3
DATE		Check or set the date	2
EMGRST		Reset internal emergency stop flag	1
ERA	<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Delete program	3
LITA	PCm-PCn	Delete program  Delete point comments "m" to "n"	3
	PLm	Delete pallet "m"	3
	Pm-Pn	Delete points "m" to "n"	3
EXELVL	k	Execution level	3
INCH			}
	k+ or k- (k : 1 to 6)	Manual movement (inching) Initialize all data (MEM+PRM)	3
INIT			ļ
	CMU	Initialize communication parameter	3
	HND	Initialize hand data	3
	LOG	Initialize error history	3
	MEM	Initialize all memory data except parameters	3
	PCM	Initialize point comment data	3
	PGM	Initialize program data	3
	PLT	Initialize pallet data	3
	PNT	Initialize point data	3

Command	Option	Meaning	Condition
	PRM	Initialize parameter data	3
	SFT	Initialize shift data	3
JOG	k+ or k- (k : 1 to 6)	Manual movement (jog)	3
MANUAL		Change mode: MANUAL mode	3
MRKSET	k (k : 1-6)	Absolute reset on each axis	3
MSGCLR		Setting Clear line message	1
MSPEED	k (k : 1-100)	Change manual speed	3
NEXT		Execute program to next line	4
ORGRTN	k (k : 1-6)	Return-to-origin	3
READ		Read data	2
REN	<pre><pre><pre><pre>program 1&gt; TO <pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre></pre>	Change program name from "1" to "2"	3
RESET		Reset program	4
RUN		Execute program	4
SEQUENCE	k	Set sequence execution flag	3
SKIP		Program: Skip one line	4
STEP		Program: Execute one line	4
STOP		Stop program	2
TEACH	m (m: point number)	Point data teaching	3
TIME		Check or set time	2
WRITE		Write data	2
-		Robot language executable independently	4

Conditions: 1. Always executable.

- 2. Not executable during inputs from the programming box.
- 3. Not executable during inputs from the programming box, and while the program is running.
- 4. Not executable during inputs from the programming box, while the program is running, and when specific restrictions apply.

# 2 Operation and setting commands

# 2.1 Program operations

# 1. Register task

#### 

# Response format

OK[cr/lf]



m ......Program number: 0 to 99
n .....Task No: 1 to 16
P .....Task priority ranking: 1 to 64

Meaning

Registers the specified program into "task n" with "priority p". The registered program enters the STOP status. When "task number n" is omitted, the task with the smallest number of those that have not been started is specified automatically. When "task priority p" is omitted, "32" is specified.

The smaller value, the higher priority. The larger value, the lower priority (high 1 to low 64). When the task with a high task priority is in the RUNNING status, the task with a low task priority still remains in the READY status.

# SAMPLE

Command: @LOAD <PG\_MAIN>, T1 [cr/lf]  $\cdots$ R e g i s t e r s t h e program to task 1. Response: OK [cr/lf]

# 2. Reset program

# 

# Response format

OK[cr/lf]



n .......Task No: 1 to 16 m ......Program number: 0 to 99 Meaning Executes the program reset.

Command format 1 resets all programs. When restarting the program, the main program or the program that has been executed last in task 1 is executed from its beginning. Command format 2 resets only the specified program. When restarting the program that has been reset, this program is executed from its beginning.

# SAMPLE

Command: @RESET [cr/lf] ······ Resets all programs.

Response: OK [cr/lf]

Command: @RESET T3 [cr/lf] ···· Resets only the program

that is executed by T3.

Response: OK [cr/lf]

# 3. Program execution

# **Command format**

# Response format

OK[cr/lf]

Values

n ......Task No: 1 to 16

m ......Program number: 0 to 99

**Meaning** 

Executes or stops the current program.

Command format 1 executes all programs in the STOP status.

Command format 2 executes only the specified program in the STOP status.

# SAMPLE

Command: @RUN [cr/lf] .... Executes all programs in

the STOP status.

Response: OK [cr/lf]

Command: @RUN T3 [cr/lf] ..... Executes only the program

in the STOP status that is

registered in T3.

•Programs can be

executed only in AUTO

mode.

# 4. Stop program

# **Command format**

# Response format

OK[cr/lf]

Values n ......Task No: 1 to 16 m .....Program number: 0 to 99

Meaning Stops the program.

Command format 1 stops all programs.

Command format 2 stops only the specified program.

# SAMPLE

Command: @STOP [cr/lf] ..... Stops all programs.

Response: OK [cr/lf]

Command: @STOP T3 [cr/lf] ······ Stops only the program

that is executed by T3.

Response: OK [cr/lf]

# 5. Execute one program line

# **Command format**

# **Command format**

OK[cr/lf]

n ......Task No: 1 to 16 m .....Program number: 0 to 99

Meaning Executes one line of the specified program. When executing one line of the GOSUB statement or CALL statement, the program operation enters the subroutine or subprocedure.

# SAMPLE

**Values** 

Command: @STEP T3 [cr/lf] ······ Executes one line of the

program that is executed

by T3.

# П

# 6. Skip one program line

# **Command format**

# Response format

OK[cr/lf]



Meaning Skips one line of the specified program. When skipping one line of the GOSUB statement or CALL statement, all subroutines or sub-procedures are skipped.

# SAMPLE

Command: @SKIP T3 [cr/lf]..... Skips one line of the

program that is executed

by T3.

Response: OK [cr/lf]

# 7. Execute program to next line

# Command format

# Response format

OK[cr/lf]

Values n ......Task No: 1 to 16 m .....Program number: 0 to 99

Meaning Executes the specified program to the next line. When executing the GOSUB statement or CALL statement, the subroutine or sub-procedure is executed one line.

# SAMPLE

Command: @NEXT T3 [cr/lf]..... Skips one line of the

program that is executed

by T3.

# 8. Execute program to line before specified line

# **Command format**

# **Command format**

OK[cr/lf]

Values

n ......Task No: 1 to 16

m ......Program number: 0 to 99

K.....Specified line number: 1 to 9999

Meaning Executes the specified program to the line before the specified line.

# SAMPLE

Command: @RUNTO T3, 15 [cr/lf] ··· Executes the program that

is executed by T3 to the

15th line.

Response: OK [cr/lf]

# 9. Skip program to line before specified line

# **Command format**

# **Command format**

OK[cr/lf]

Values

n ......Task No: 1 to 16

m ......Program number: 0 to 99

K.....Line number to set a break point: 1 to 9999

Meaning Skips the specified program to the line before the specified line.

# SAMPLE

Command: @SKIPTO T3, 15 [cr/lf] ·· Skips the program that is

executed by T3 to the 14th

line.

# 10. Set break point

# **Command format**

# **Command format**

OK[cr/lf]

Meaning Sets a break point to pause the program during program execution.

Command format 1 sets or cancels a break point in the specified line of the specified program. Multiple lines can also be specified.

Command format 2 cancels all break points set in the specified program.

Command format 3 cancels all break points.

# SAMPLE

Command:@BREAK PG3 (1, 3), 1 [cr/lf]  $\cdots$  Sets a break point in the first and third lines of PG3.

Response: OK [cr/lf]

8

9

10

11

# 2.2 MANUAL mode operation

# ■ 1. Changing the MANUAL mode speed

# **Command format**

@MSPEED[<robot number>] k[cr/lf]

# Response format

OK[cr/lf]

Values

<robot number>......1 to 4

k .......Manual movement speed: 1 to 100

Meaning Changes the manual mode movement speed of the robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified.

# SAMPLE

Command: @MSPEED 50[cr/lf]

Response: OK[cr/lf]

# 2. Point data teaching

# **Command format**

@TEACH[<robot number>] mmmmmm[cr/lf]
@TCHXY[<robot number>] mmmmmm[cr/lf]

# Response format

OK[cr/lf]

Values

<robot number>.....1 to 4

mmmmm ......Point number for registering point data: 0 to 29999

Meaning

Registers the current robot position as point data for the specified point number. If point data is already registered in the specified point number, then that point data will be overwritten.

The unit of the point data may vary depending on the command.

TEACH ....."pulse" units
TCHXY ....."mm" units

#### SAMPLE

Command: @TEACH 100[cr/lf]

# П

# 2.3 Clearing output message buffer

# **Command format**

@MSGCLR [cr/lf]

# Response format

OK[cr/lf]

Values

Clears the output message buffer of the controller. After the messages have been output by the PRINT statement, etc., the messages remaining in the buffer are cleared.

# SAMPLE

Command: @MSGCLR [cr/lf]

Response: OK[cr/lf]

# 2.4 Setting input data

# **Command format**

@INPUT | SET d | ([cr/lf] CAN | CLR

# Response format

OK[cr/lf]

Values

d: Input data......Value that is matched to the type of the variable specified by the INPUT statement.

(Character string is enclosed by " ".)

Meaning Sets the input data to the data request by the INPUT statement.

SET Sets the data.

CAN Cancels the data request.

CLR Clears the data that is not received by the controller.

# SAMPLE

Command: @INPUT "DATA" [cr/lf]

# 3 Reference commands

# 3.1 Acquiring return-to-origin status

# Command format 1

@?ORIGIN[cr/lf]

# Response format 1

x [cr/lf] OK [cr/lf]]

# Command format 2

@?ORIGIN <robot number> [cr/lf]

# Response format 2

x y{,y{,{...}}} [cr/lf] OK [cr/lf]

Values

<robot number>.....1 to 4

x: Robot return-to-origin status..0: Incomplete, 1: Complete

y: Axis return-to-origin status..Shows the status of the axis 1, axis 2, ..., axis 6 from the left.

0: Incomplete, 1: Complete (Omitted when the axis is not connected.)

Meaning

Acquires return-to-origin status.

Command format 1 acquires the return-to-origin status of all robots while command format 2 acquires the status of the specified robot.

# SAMPLE

Command: @?ORIGIN 2 [cr/lf]

Response: 0 1,1,0,1 ······ Axis 3 of the robot 2 is

in the return-to-origin

incomplete status.

OK [cr/lf]

10

# 3.2 Acquiring the servo status

#### **Command format**

@?SERVO [<robot number>] [cr/lf]

# Response format

Values

<robot number>......1 to 4

x: Robot servo status ......0: Servo off status, 1: Servo on status

y: Axis servo status ......Shows the status of the axis 1, axis 2, ..., axis 6 from the left.

0: Mechanical brake on + dynamic brake on status

1: Servo on status

2: Mechanical brake off + dynamic brake off status

(Omitted when the axis is not connected.)

Meaning Acquires the servo status. <robot number> can be omitted. If it is omitted, robot 1 is specified.

# SAMPLE

Command: @?SERVO[3] [cr/lf]

Response: 0 0,1,0,0  $\cdots$  Only the axis 2 of the

robot 3 is in the servo on

status.

OK [cr/lf]

# 3.3 Acquire motor power status

# **Command format**

@?MOTOR [cr/lf]

# Response format

x [cr/lf] OK [cr/lf]

Values

x: Motor power status......0: Motor power off status

1: Motor power on status

2: Motor power on + all robot servo on status

Meaning Acquires the motor power status.

# SAMPLE

Command: @?MOTOR [cr/lf]

Response: 2

OK [cr/lf]

 For a detailed description of the access level, refer

to the Controller user's

manual.

# 3.4 Acquiring the access level

# **Command format**

@?ACCESS[cr/lf]

# Response format

LEVELk[cr/lf]



k ......Access level: 0 to 1

Meaning Acquires the access level.

SAMPLE

Command: @?ACCESS[cr/lf]

Response: 1[cr/lf]

OK[cr/lf]

# 3.5 Acquiring the break point status

# **Command format**

@?BREAK[cr/lf]

# Response format

k1, k2, k3, k4 [cr/lf]

Values

kn .....Line number on which break point "n" is set: 1 to 9999

Meaning

Acquires the break point status.

When kn is 0, this means no break point is set.

When a break point is set in the COMMON program, the line number shows +10000.

# SAMPLE

Command: @?BREAK[cr/lf]
Response: 12,35,0,0[cr/lf]

@?MODE[cr/lf]

Response format

k[cr/lf] OK[cr/lf]

Values

k ......Mode status

Meaning Acquires the controller mode status.

SAMPLE

Command: @?MODE[cr/lf]

Response: 1[cr/lf]

OK[cr/lf]

# 3.7 Acquiring the sequence program execution status

# **Command format**

@?SEQUENCE[cr/lf]

# Response format

- 1. 1,s[cr/lf]
- 2. 3,s[cr/lf]
- 3. 0[cr/lf]

Values

s......The sequence program's execution status is indicated

as 1 or 0.

1 ......Program execution is in progress.

0 ......Program execution is stopped.

Meaning

Acquires the sequence program execution status.

Response output means as follows:

1 .....Enabled

3 ......Enabled and output is cleared at emergency stop

0 ......Disabled

SAMPLE

Command: @? SEQUENCE[cr/lf]

Response: 0[cr/lf]

7

8

9

10

п

#### Acquiring the version information 3.8

# **Command format**

@?VER[cr/lf]

#### Response format

cv, cr-mv-dv1, dr1/dv2, dr2[cr/lf]

**Values** 

CV	Host version number
cr	Host revision number (Rxxxx)
mv	PLO version number (Vx.xx)
dv? (?: 1, 2)	Driver version number (Vx.xx)
dr? (?: 1, 2)	Driver revision number (Rxxxx)

Meaning Acquires the version information.

# SAMPLE

Command: @?VER[cr/lf]

Response: V8.02,R1021-V5.10-V1.01,R0001/V1.01,R0001[cr/lf]

#### 3.9 Acquiring the current positions

# 1. Acquiring the current positions on pulse unit coordinates

# Command format

@?WHERE[cr/lf]

# Response format

xxxxxx yyyyyy zzzzzz rrrrrr aaaaaa bbbbbb[cr/lf]

Values

bbbbbb ......Current position of axis 6 in "pulse" units

Meaning Acquires the current positions.

WHERE: Acquires the current position of the specified robot.

# SAMPLE

@?WHERE[cr/lf] Command:

0 [cr/lf] Response: 1000 2000 3000 -40000 0

## 2. Acquiring the current positions on XY coordinates

#### **Command format**

@?WHRXY[cr/lf]

#### Response format

xxxxxx yyyyyy zzzzzz rrrrrr aaaaaa bbbbbb[cr/lf]

Values

yyyyyy .......Current position of axis 2 in "mm" or "deg" units

Acquires the current positions.

WHRXY: Acquires the current positions of the specified robot..

SAMPLE

Command: @?WHRXY[cr/lf]

Response: 100.00 200.00 300.00 -40.00 0.00 0.00[cr/lf]

#### Acquiring the tasks in RUN or SUSPEND status 3.10

#### **Command format**

@?TASKS[cr/lf]

#### Response format

n{,n{,{...}}} [cr/lf]

Values

n: Task number ......1 to 16 (Task currently run or suspended)

Meaning Acquires the tasks in RUN or SUSPEND status.

SAMPLE

Command: @?TASKS[cr/lf] Response: 1,3,4,6[cr/lf]

10

# 3.11 Acquiring the tasks operation status

#### **Command format**

@?TSKMON[cr/lf]

#### Response format

nfp, {nfp}, {nfp}, {nfp}, {nfp}, {nfp}, {nfp}, {nfp}, {nfp} [cr/lf]

Values

Meaning Acquires the status of each task in order from Task 1 to Task 8.

#### SAMPLE

Command: @?TSKMON[cr/lf]

Response: 11R32,,43U32,,,,129R31,[cr/lf]

# 3.12 Acquiring the shift status

#### **Command format**

@?SHIFT[<robot number>][cr/lf]

#### Response format

m[cr/lf]

Values

<robot number>......1 to 4
m ......Shift number selected for the specified robot: 0 to 39

Meaning Acquires the shift status of the robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified.

#### SAMPLE

Command: @?SHIFT[cr/lf]

Response: 1[cr/lf]

OK[cr/lf]

@?HAND[<robot number>][cr/lf]

Response format

m[cr/lf]

Values <robot number>......1 to 4

m ......Hand number selected for the specified robot: 0 to 31

Meaning Acquires the hand status of the robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified.

SAMPLE

Command: @?HAND[cr/lf]

Response: 1[cr/lf]

OK[cr/lf]

# 3.14 Acquiring the remaining memory capacity

#### **Command format**

@?MEM[cr/lf]

#### Response format

k/m[cr/lf]

Values

m ......Remaining global identifier area (unit: bytes)

Meaning Acquires the remaining memory capacity.

SAMPLE

Command: @?MEM[cr/lf]

Response: 102543/1342[cr/lf]

OK[cr/lf]

7

8

9

10

11

# 3.15 Acquiring the emergency stop status

#### **Command format**

@?EMG[cr/lf]

#### Response format

k[cr/lf]

Values

k ......Emergency stop status / 0: normal operation,
1: emergency stop

Meaning Acquires the emergency stop status by checking the internal emergency stop flag.

#### SAMPLE

# 3.16 Acquiring various values

## 1. Acquiring the value of a numerical expression

#### Command format

@? "numerical expression" [cr/lf]

#### Response format

"numerical value" [cr/lf]

Meaning Acquires the value of the specified numerical expression.

The numerical expression's value format is "decimal" or "real number".

#### SAMPLE 1

Command: @?SQR(100\*5)[cr/lf]
Response: 2.23606E01[c/lf]

OK[cr/lf]

#### SAMPLE 2

Command: @?LOC1(WHERE)[cr/lf]

Response: 102054[cr/lf]

OK[cr/lf]

## 2. Acquiring the value of a character string expression

#### **Command format**

@? "character string expression" [cr/lf]

#### Response format

"character string " [cr/lf]

Meaning Acquires the value (character string) of the specified character string expression.

#### SAMPLE

If A\$="ABC" and B\$="DEF"

Command: @?A\$+B\$+"123"[cr/lf]
Response: ABCDEF123[cr/lf]

OK[cr/lf]

## 3. Acquiring the value of a point expression

#### Command format

@? "point data expression" [cr/lf]

#### Response format

"point data" [cr/lf]

Meaning Acquires the value (point data) of the specified point expression.

#### SAMPLE

Command: @?P1+WHRXY[cr/lf]

Response: 10.41 -1.60 52.15 3.00 0.00 0.00 0[cr/lf]

OK[cr/lf]

#### 4. Acquiring the value of a shift expression

#### **Command format**

@? "shift expression" [cr/lf]

#### Response format

"shift data" [cr/lf]

Meaning Acquires the value (shift data) of the specified shift expression.

#### SAMPLE

Command: @?s1[cr/lf]

Response: 25.00 12.60 10.00 0.00[cr/lf]

OK[cr/lf]

# 4 Operation commands

# 4.1 Absolute reset

#### **Command format**

@ABSADJ [<robot number>] k,f[cr/lf]
@MRKSET [<robot number>] k[cr/lf]

#### **Response format**

At the start of movement: RUN[cr/lf]
At the completion of movement: END[cr/lf]

Values

Meaning

Performs the absolute reset operation of a robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified.

ABSADJ......Moves the specified robot axis to an absolute reset position.

MRKSET ......Performs absolute reset on the specified robot axis.

#### SAMPLE

Command: @ABSADJ 1,0[cr/lf]

Response: RUN[cr/lf] ..... Start of movement

END[cr/lf] ..... Completion of movement



ABSADJ and MRKSET can be used at mark format axes.

@ORGRTN[<robot number>] k[cr/lf]

#### Response format

At the start of movement: RUN[cr/lf]
At the completion of movement: END[cr/lf]

Values

<robot number>......1 to 4 k ......Specified axis: 1 to 6

Meaning

Performs the return-to-origin operation on the specified axis of the robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified. For the axis with the semi-absolute specifications, when the return-to-origin is executed, the absolute search operation is performed.

#### SAMPLE

Command: @ORGRTN 1[cr/lf]

Response: RUN[cr/lf] ..... Start of movement

END[cr/lf] ..... Completion of movement

9

10

П

# 4.3 Manual movement: inching

#### **Command format**

@INCH [<robot number>] km [cr/lf] @INCHXY [<robot number>] km [cr/lf] @INCHT [<robot number>] km [cr/lf]

#### Response format

At the start of movement: RUN[cr/lf]
At the completion of movement: END[cr/lf]

 Values
 <robot number>......1 to 4

 k
 Specified axis: 1 to 6

 m
 Movement direction / +,

Manually moves (inching motion) the specified axis of the robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified. The robot performs the same motion as when moved manually in inching motion with the programming box jog keys (moves a fixed distance each time a jog key is pressed). The unit of the movement amount and operation type by command are shown below.

INCH ....."pulse" units. Only the specified axis moves.

INCHXY ....."mm" units. According to the robot configuration, the arm tip of the robot moves in the direction of the Cartesian coordinate system.

INCHT ....."mm" units. According to the robot configuration, the hand attached to the arm tip of the robot moves.

#### SAMPLE

Command: @INCH 1+[cr/lf]

Response: RUN [cr/lf] ..... Start of movement

END [cr/lf] ..... Completion of movement

10

#### Command format

@JOG [<robot number>] km [cr/lf] @JOGXY [<robot number>] km [cr/lf] @JOGT [<robot number>] km [cr/lf]

#### Response format

At the start of movement: RUN[cr/lf]
At the completion of movement: END[cr/lf]

Values

<robot number>......1 to 4
k ......Designated axis: 1 to 6
m ......Movement direction / +, -

Meaning

Manually moves (jog motion) the specified axis of the robot specified by the <robot number>. <robot number> can be omitted. If it is omitted, robot 1 is specified. The robot performs the same motion as when holding down the programming box jog keys in manual mode.

To continue the operation, it is necessary for the JOG command to input the execution continue process ( $^{\text{V}}(=16\text{H})$ ) by the online command at intervals of 200ms. If not input, the error stop occurs.

Additionally, after the movement has started, the robot stops when any of the statues shown below arises.

- When software limit was reached.
- When interlock signal was turned off.
- When STOP key on the programming box was pressed.
- When an online command (^C (=03H)) to interrupt execution was input.

The unit of the movement amount and operation type by command are shown below.

JOG ....."pulse" units. Only the specified axis moves.

JOGXY....."mm" units. According to the robot configuration, the arm tip of the robot moves in the direction of the Cartesian coordinate system.

JOGT ....."mm" units. According to the robot configuration, the hand attached to the arm tip of the robot moves.

#### SAMPLE

Command: @JOG 1+[cr/lf]

Response: RUN[cr/lf] ..... Start of movement

END[cr/lf] ..... Completion of movement

5

# Data file operation commands

# 5.1 Copy operations

## 1. Copying a program

#### **Command format**

#### Response format

At process start: RUN [cr/lf]
At process end: END [cr/lf]

Values

#### SAMPLE

Command: @COPY <TEST1> TO <TEST2> [cr/lf]
Response: RUN [cr/lf] ...... Process start
END [cr/lf] ..... Process end

#### 2. Copying point data

#### Command format

@COPY Pmmmmm-Pnnnnn TO Pkkkkk[cr/lf]

#### Response format

At process start: RUN [cr/lf] At process end: END [cr/lf]

Values

mmmmm .......Top point number in copy source: 0 to 29999
nnnnn ......Last point number in copy source: 0 to 29999
kkkkk .......Top point number in copy destination: 0 to 29999

Meaning Copies the point data between Pmmmmm and Pnnnnn to Pkkkkk.

#### SAMPLE

Command: @COPY P101-P200 TO P1101[cr/lf]
Response: RUN [cr/lf] ...... Process start
END [cr/lf] ..... Process end

#### 3. Copying point comments

#### **Command format**

@COPY PCmmmmm-PCnnnnn TO PCkkkkk[cr/lf]

#### Response format

At process start: RUN [cr/lf] At process end: END [cr/lf]

Values

Meaning Copies the point comments between PCmmmmm and PCnnnnn to PCkkkkk.

#### SAMPLE

Command: @COPY PC101-PC200 TO PC1101[cr/lf]
Response: RUN [cr/lf] ...... Process start
END [cr/lf] ..... Process end

#### 5.2 Erase

## 1. Erasing a program

#### **Command format**

#### Response format

At process start: RUN [cr/lf]
At process end: END [cr/lf]

Values

Meaning Erases the designated program.

#### SAMPLE

Command: @ERA <TEST1> [cr/lf]

Response: RUN [cr/lf]  $\cdots$  Process start END [cr/lf]  $\cdots$  Process end

#### 2. Erasing point data

#### **Command format**

@ERA Pmmmmm-Pnnnnn[cr/lf]

#### Response format

At process start: RUN [cr/lf]
At process end: END [cr/lf]

Values

Meaning Erases the point data between Pmmmmm and Pnnnnn.

#### SAMPLE

Command: @ERA P101-P200[cr/lf]

Response: RUN [cr/lf] ...... Process start END [cr/lf] ..... Process end

#### 3. Erasing point comments

#### **Command format**

@ERA PCmmmmm-PCnnnnn[cr/lf]

#### Response format

At process start:RUN [cr/lf]
At process end:END [cr/lf]

Values

Meaning Erases the point comments between PCmmmmm and PCnnnnn.

#### SAMPLE

Command: @ERA PC101-PC200[cr/lf]

Response: RUN [cr/lf] ..... Process start

END [cr/lf] ..... Process end

#### 4. Erasing point name

#### **Command format**

@ERA PNmmmmm-PNnnnnn [cr/lf]

#### Response format

At process start: RUN [cr/lf]
At process end: END [cr/lf]

-

mmmmm ......Top point name number to be erased: 0 to 29999
nnnnn .....Last point name number to be erased: 0 to 29999

Meaning Erases the point names between PNmmmmm and PNnnnnn.

#### SAMPLE

Values

Command: @ERA PC101-PC200[cr/lf]

Response: RUN [cr/lf]  $\cdots$  Process start END [cr/lf]  $\cdots$  Process end

#### 5. Erasing pallet data

#### **Command format**

@ERA PLm[cr/lf]

#### Response format

At process start:RUN [cr/lf] At process end:END [cr/lf]

Values

m ......Pallet number to be erased: 0 to 39

Meaning Erases the PLm pallet data.

#### SAMPLE

Command: @ERA PL1[cr/lf]

Response: OK[cr/lf]

#### 6. Erasing hand

#### **Command format**

@ERA Hm [cr/lf]

#### Response format

At process start: RUN [cr/lf]
At process end: END [cr/lf]

Values

m ......Hand number to be erased: 0 to 31

Meaning Erases the hand definition data of "Hm".

#### SAMPLE

Command: @ERA H2 [cr/lf]

Response: RUN [cr/lf] ..... Process start

END [cr/lf] ..... Process end

### 7. Erasing shift

#### **Command format**

@ERA Sm [cr/lf]

#### Response format

At process start:RUN [cr/lf] At process end:END [cr/lf]

Values

m ......Shift number to be erased: 0 to 39

Meaning Erases the shift data of "Sm".

#### SAMPLE

Command: @ERA S1 [cr/lf]

Response: RUN [cr/lf] ..... Process start

 ${\tt END} \; [{\tt cr/lf}] \; \cdots \cdots \; {\tt Process} \; \; {\tt end} \; \;$ 

#### 8. Erasing area check output setting

#### **Command format**

@ERA ACm [cr/lf]

#### **Response format**

At process start: RUN [cr/lf] At process end: END [cr/lf]

Values m ......Area check output setting number to be erased: 0 to 31

Meaning Erases the area check output setting of "ACm".

#### SAMPLE

Command: @ERA AC3 [cr/lf]

Response: RUN [cr/lf] ...... Process start END [cr/lf] ..... Process end

## 9. Erasing general-purpose Ethernet port

#### **Command format**

@ERA GPm [cr/lf]

#### Response format

At process start: RUN [cr/lf]
At process end: END [cr/lf]

Values m ......General-purpose Ethernet port number to be erased: 0 to 15

Meaning Erases the general-purpose Ethernet port of "GPm".

#### SAMPLE

Command: @ERA GP5 [cr/lf]

Response: RUN [cr/lf] ...... Process start END [cr/lf] ..... Process end

# 5.3 Rename program name

#### **Command format**

@REN cprogram name 1> TO cprogram name 2> [cr/lf]

#### **Response format**

At process start:RUN [cr/lf] At process end:END [cr/lf]

Values

n: Program number ......0 to 99

Meaning Changes the name of the specified program.

#### SAMPLE

Command: @REN < TEST1> TO < TEST2> [cr/lf] Response: RUN [cr/lf]  $\cdots$  Process start END [cr/lf]  $\cdots$  Process end

# 5.4 Changing the program attribute

#### **Command format**

#### Response format

OK[cr/lf]

Values

#### SAMPLE

Command: @ATTR <TEST1> TO RO[cr/lf]

Response: OK[cr/lf]

#### **Command format**

@INIT <memory area>[cr/lf]

#### Response format

At process start: RUN [cr/lf] At process end: END [cr/lf]

Values

One of the following memory areas is specified. PGM ......Initializes the program area. PNT ......Initializes the point data area. SFT......Initializes the shift data area. HND.....Initializes the hand data area. PLT ......Initializes the pallet data area. PCM......Initializes the point comment area. PNM ......Initializes the point name area. ACO ......Initializes the area check output setting area. GEP......Initializes the general-purpose Ethernet port setting area. MEM ......Initializes the above areas (PGM ... all data up to PCM). PRM......Initializes the parameter area. ALL ......Initializes all areas (MEM+PRM).

**Meaning** Initializes the memory area.

#### SAMPLE

Command: @INIT PGM[cr/lf]

RUN [cr/lf] ..... Process start Response:

END [cr/lf] ..... Process end

#### 2. Initializing the communication port

#### **Command format**

@INIT <communication port> [cr/lf]

#### Response format

At process start: RUN [cr/lf] At process end: END [cr/lf]

Values

<communication port> .........Communication port to be initialized Specify any of the ports shown below for the communication port.

CMU.....Initializes the RS-232C port. ETH......Initializes the Ethernet port.

Meaning

Initializes the communication port.

For information about the communication port initial settings, refer to the Controller user's manual.

#### SAMPLE

@INIT CMU [cr/lf] Command:

Response: RUN [cr/lf] ..... Process start

END [cr/lf] ..... Process end

## 3. Initializing the alarm log

#### **Command format**

@ INIT LOG[cr/lf]

#### Response format

At process start: RUN [cr/lf] At process end: END [cr/lf]

Meaning Initializes the error log.

#### SAMPLE

Command: @INIT LOG[cr/lf]

Response: OK[cr/lf]

#### **Command format**

@READ <readout file> [cr/lf]

#### Response format

At process start: BEGIN [cr/lf]

(Data output: The contents may vary depending on

the readout file.)

At process end: END [cr/lf]



• For more information about files, refer to the earlier Chapter 8 "Data file description".

Values

<readout file> ...... Designate a readout file name.

**Meaning** 

Reads out the data from the designated file.

Online commands that are input through the RS-232C port have the same meaning as the following command.

• SEND <readout file> TO CMU

Commands via Ethernet have the same meaning as the following command.

• SEND <readout file> TO ETH

Tuno	Readout file name	Definit	ion format
Туре	Headout file name	All	Separate file
User memory	All files	ALL	
	Program	PGM	<bbb>&gt;</bbb>
	Point data	PNT	Pn
	Point comment	PCM	PCn
	Point name	PNM	PNn
	Parameter	PRM	/ccccccc/
	Shift definition	SFT	Sn
	Hand definition	HND	Hn
	Pallet definition	PLT	PLn
	General-purpose Ethernet port	GEP	GPn
	Input/output name	ION	iNMn(n)
	Area check output	ACO	ACn
Variable, constant	Variable	VAR	abby
	Array variable	ARY	abby(x)
	Constant		"ccc"
Status	Program directory	DIR	< <bbb>&gt;</bbb>
	Parameter directory	DPM	
	Machine reference	MRF	
	Machine reference (mark axis)	ARP	
	Controller configuration	CFG	
	Option board	OPT	
	Self-diagnosis	SCK	
	Alarm log	LOG	
Device	DI port	DI()	DIn()
	DO port	DO()	DOn()
	MO port	MO()	MOn()
	TO port	TO()	TOn()
	LO port	LO()	LOn()
	SI port	SI()	SIn()
	SO port	SO()	SOn()
	SIW port	SIW()	SIWn()
	SOW port	SOW()	SOWn()
Others	File end code	EOF	V

a: Alphabetic character b: Alphanumeric character or underscore ( \_ ) c: Alphanumeric character or symbol i: I/O type n: Number x: Expression (Array argument) y: variable type

#### SAMPLE

Command: @READ PGM [cr/lf]

@READ P100 [cr/lf]

@READ DINM2(0) [cr/lf]

#### Data write processing 5.7

#### **Command format**

@WRITE <write file> [cr/lf]

#### Response format

Input request display ▶ READY[cr/lf] After input is completed ▶ OK [cr/lf]

For more information about files, refer to the earlier Chapter 8 "Data file description".



<write file> ...... Designate a write file name.

#### (Meaning)

Writes the data in the designated file.

Online commands that are input through the RS-232C port have the same meaning as the following command.

• SEND CMU TO <write file>

Commands via Ethernet have the same meaning as the following command.

• SEND ETH TO <write file>



- At the DO, MO, TO, LO, SO, SOW ports, an entire port (DO(), MO(), etc.) cannot be designated as a WRITE file.
- Some separate files (DOn(), MOn(), etc.) cannot be designated as a WRITE file. For details, see Chapter 8 "Data file description".

Tuno	Write file name	Defi	nition format
Туре	write nie name	All	Separate file
User memory	User memory All files ALL Program PGM		
			<bbb>&gt;</bbb>
	Point data	PNT	Pn
	Point comment	PCM	PCn
	Point name	PNM	PNn
	Parameter	PRM	/ccccccc/
	Shift definition	SFT	Sn
	Hand definition	HND	Hn
	Pallet definition	PLT	PLn
	General-purpose Ethernet port	General-purpose Ethernet port GEP	
	Input/output name ION		iNMn(n)
	Area check output	ACO	ACn
Variable, constant	Variable	VAR	abby
	Array variable	ARY	abby(x)
Device	DO port		DOn()
	MO port		MOn()
	TO port  LO port		TOn()
			LOn()
	SO port		SOn()
	SOW port		SOWn()

a: Alphabetic character b: Alphanumeric character or underscore ( \_ ) c: Alphanumeric character or symbol i: I/O type x: Expression (Array argument) y: variable type

#### SAMPLE

Command: @WRITE PRM [cr/lf]

@WRITE P100 [cr/lf]

@WRITE DINM2(0) [cr/lf] f]

# 10

#### Setting the sequence program execution flag 6.1

#### Command format

@SEQUENCE k[cr/lf]

#### Response format

OK[cr/lf]

Values

k ...... Execution flag / 0: disable, 1: enable, 3: enable (DO reset)

Meaning Sets the sequence program execution flag.

#### SAMPLE

@ SEQUENCE 1[cr/lf] Command:

Response: OK[cr/lf]

#### 6.2 Setting the date

#### **Command format**

@DATE yy/mm/dd[cr/lf]

•To change only the year or month, the slash (/) following it can be omitted.

Example:

To set the year to 2007, enter 07(cr/lf).

To set the month to June, enter /06(cr/lf).

#### Response format

OK[cr/lf]



yy/mm/dd	Date to be set. (year, month, day)
уу	Lower 2 digits of the year (00 to 99)
mm	Month (01 to 12)
dd	Day (01 to 31)

Meaning Sets a date in the controller



- The currently set values are used for the omitted items.
- If only [cr/lf] is transmitted, then the date remains unchanged.
- If an improbable date is entered, then "5.2: Data error" occurs.

#### SAMPLE 1

```
To change only the day,
 //15[cr/lf] ..... Day is set to 15th.
```

#### SAMPLE 2

@DATE 14/01/14[cr/lf] Command:

OK[cr/lf] Response:

#### Setting the time 6.3

#### **Command format**

@TIME hh:mm:ss[cr/lf]

#### Response format

OK[cr/lf]



hh:mm:ss	Current time
hh	hour (00 to 23)
mm	minute (00 to 59)
ss	second (00 to 59)

Meaning Sets the time of the controller.



- The currently set values are used for the omitted items.
- If only [cr/lf] is transmitted, then the time remains unchanged.
- If an improbable time is entered, then "5.2: Data error" occurs.

#### SAMPLE 1

```
To change only the minute,
 :20: [cr/lf] ······ Minute is set to 20 minutes.
```

## SAMPLE 2

@TIME 10:21:35[cr/lf] Command:

Response: OK[cr/lf]

# Executing the robot language independently

#### **Command format**

@"robot language"[cr/lf]

#### Response format 1

OK[cr/lf] or NG=gg.eee [cr/lf]

#### Response format 2

At process start: RUN [cr/lf] or NG=gg.eee [cr/lf] At process end: END [cr/lf] or NG=gg.eee [cr/lf]

#### Values

OK, END...... Command ended correctly.

NG....... An error occurred.

RUN ...... Command starts correctly.

gg: Alarm group number ...... 0 to 99

ccc: Alarm classification number ...... 0 to 999

#### Meaning

Robot language commands can be executed.

- Independently executable commands can only be executed.
- Command format depends on each command to be executed.

#### SAMPLE 1

Command: @SET DO(20) [cr/lf]

Response: OK[cr/lf]

#### SAMPLE 2

Command: @MOVE P, P100, S=20[cr/lf]

Response: RUN [cr/lf] ..... Process start

END [cr/lf] ..... Process end

9

10

П

# 8 Control codes

# Command format

^C (=03H)

### Response format

NG=1.8

Meaning Interrupts execution of the current command.

#### SAMPLE

Command: @MOVE P,P100,S=20[cr/lf]

^C

Response: NG=1.8[cr/lf]

# Chapter 11 Appendix

1	Reserved word list11-1
2	Robot Language Lists: Command list in alphabetic order $11-3$
3	Robot Language Lists: Function Specific 11-7
4	Functions: in alphabetic order11-12
5	Functions: operation-specific11-14

# Reserved word list

The words shown below are reserved for robot language and cannot be used as identifiers (variables, etc.).

A	DEC	HND	MOVET
ABS	DECEL	HOLD	MRF
ABSADJ	DEF	HOLDALL	MRKSET
ABSRPOS	DEGRAD	I	MSG
ACC	DELAY	IDIST	MSGCLR
ACCEL	DI	IF	MSPEED
ACCESS	DIM	IMP	N
ACO	DIR	INCH	NAME
ALL	DIST	INCHT	NEXT
ALM	DO	INCHXY	NOT
ALMRST	DPM	INIT	0
AND	DRIVE	INPUT	OFF
ARCHP1	DRIVEI	INT	OFFLINE
ARCHP2	DRV	ION	ON
• ARM	DS	J	ONLINE
ARMCND	DSPEED	JL	OPEN
ARMSEL	Е	JOG	OPT
ARMTYP	ELSE	JOGT	OR
ARP	ELSEIF	JOGXY	ORD
ARY	EMG	JTOXY	ORGORD
ASPEED	END	L	ORGRTN
ATN	ENDIF	LEFT	ORIGIN
ATN2	EOF	LEFTY	OUT
ATTR	EQV	LEN	OUTPOS
AXWGHT	ERA	LET	Р
В	ERL	LINEMODE	Р
BIN	ERR	LOAD	PATH
BREAK	ERROR	LOC1	PC
С	ETH	LOC2	PCM
CALL	ETHSTS	LOC3	PDEF
CASE	EXIT	LOC4	PGM
CFG	EXITTASK	LOC5	PGMTSK
CHANGE	F	LOC6	PGN
CHGPRI	FN	LOCF	PLS
CHR	FOR	LOG	PLT
CLOSE	FREE	LSHIFT	PMOVE
CMU	G	M	PNM
CNT	GEP	MAINPG	PNT
CONT	GEPSTS	MCHREF	PPNT
COPY	GO	MEM	PRINT
COS	GOSUB	MID	PRM
CURTQST	GOTO	MNS	PSHFRC
CURTRQ	Н	MOD	PSHJGSP
CUT	HALT	MODE	PSHMTD
D	HALTALL	MOTOR	PSHRSLT
DATE	HAND	MOVE	PSHSPD
		1	1

PUSH	SET	SWI	VEL
PWR	SETGEP	SYNCHK	VER
R	SETPW	Т	W
RADDEG	SFT	XYTOJ	WAIT
RBT	SGI	Υ	WEIGHT
READ	SGR	YZ	WEND
REF	SHARED	Z	WHERE
REM	SHIFT	TAG	WHILE
REN	SI	TAN	WHRXY
RESET	SID	TASKS	WHRXYEX
RESTART	SIN	TCHXY	WRITE
RESUME	SIW	TCOUNTER	X
RETURN	SKIP	TEACH	XOR
RIGHT	SKIPTO	THEN	XY
RIGHTY	SO	TIM	XYTOJ
RSHIFT	SOD	TIME	Υ
RUN	SOW	TIMER	YZ
RUNTO	SPEED	ТО	Z
S	SQR	TOLE	ZX
S	START	TORQUE	
SCK	STEP	TSKECD	
SELECT	STOP	TSKMON	
SEND	STOPON	TSKPGM	
SEQCMPL	STR	V	
SEQUENCE	SUB	VAL	
SERVO	SUSPEND	VAR	

Because the following names are used as system variable names, they cannot be used at the beginning of other variable names (n: numeric value).

Acn	FN	PCn	Sn	
Dln	GPn	Pn	Son	
DINMn	Hn	PNn	SONMn	
DOn	LOn	SIn	TOn	
DONMn	MOn	SINMn		

### Variable name usage examples

• Although keywords which are reserved as robot language words cannot be used as they are, they can be used as variable names if alphanumeric characters are added to them.

Example: "ABS" cannot be used, but "ABS1" or "ABSX" can be used.

• Keywords reserved as system variables cannot be used at the beginning of other variable names, even if alphanumeric characters are added to them.

Example: "FN" cannot be used. "FNA" and "FN123" also cannot be used.

No.	Command	Function	Online	Туре
Α				
1	ABS	Acquires the absolute value of a specified value.	-	Command Statements
2	ABSRPOS	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)	-	Command Statements/ Functions
3	ACCEL	Specifies/acquires the acceleration coefficient parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP1	Specifies/acquires the arch position 1 parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP2	Specifies/acquires the arch position 2 parameter of a specified robot.	0	Command Statements/ Functions
5	ARMCND	Acquires the current arm status of a specified robot.	-	Functions
6	ARMSEL	Acquires the current "hand system" setting of a specified robot.	-	Functions
7	ARMTYP	Acquires the "hand system" setting of a specified robot.	-	Functions
8	ASPEED	Specifies/acquires the AUTO movement speed of a specified robot.	0	Command Statements/ Functions
9	ATN	Acquires the arctangent of the specified value.	-	Functions
9	ATN2	Acquires the arctangent of the specified X-Y coordinates.	-	Functions
10	AXWGHT	Specifies/acquires the axis tip weight parameter of a specified robot.	0	Command Statements/ Functions
С				
11	CALL	Calls a sub-procedure.	×	Command Statements
12	CHANGE	Switches the hand of a specified robot.	0	Command Statements
13	CHGPRI	Changes the priority ranking of a specified task.	0	Command Statements
14	CHR\$	Acquires a character with the specified character code.	-	Functions
15	cos	Acquires the cosine value of a specified value.	-	Functions
16	CURTQST	Acquires the current torque against the rated torque of a specified axis.	-	Functions
17	CURTRQ	Acquires the current torque value of the specified axis of a specified robot.	-	Functions
18	CUT	Terminates a task currently being executed or temporarily stopped.	0	Command Statements
D				
19	DATE\$	Acquires the date as a "yy/mm/dd" format character string.	-	Functions
20	DECEL	Specifies/acquires the deceleration rate parameter of a specified robot.	0	Command Statements/ Functions
21	DEF FN	Defines the functions that can be used by the user.	×	Command Statements
22	DEGRAD	Converts a specified value to radians (↔RADDEG).	-	Functions
23	DELAY	Waits for the specified period (units: ms).	×	Command Statements
24	DI	Acquires the input from the parallel port.	-	Functions
25	DIM	Declares the array variable name and the number of elements.	×	Command Statements
26	DIST	Acquires the distance between 2 specified points.	-	Functions
27	DO	Outputs a specified value to the DO port.	0	Command Statements
28	DRIVE	Moves a specified axis of a specified robot to an absolute position.	0	Command Statements
28	DRIVE	(With T-option) Executes an absolute movement command for a specified axis.	0	Command Statements
29	DRIVEI	Moves a specified axis of a specified robot to a relative position.	0	Command Statements

No.	Command	Function	Online	Туре
E				
30	END SELECT	Terminates the SELECT CASE statement.	×	Command Statements
31	END SUB	Terminates the sub-procedure definition.	×	Command Statements
32	ERL	Gives the line No. where an error occurred.	-	Functions
32	ERR	Gives the error code number of an error which has occurred.	-	Functions
33	EXIT FOR	Terminates the FOR to NEXT statement loop.	×	Command Statements
34	EXIT SUB	Terminates the sub-procedure defined in SUB to END.	×	Command Statements
35	EXIT TASK	Terminates its own task which is in progress.	×	Command Statements
F				
36	FOR to NEXT	Controls repetitive operations. Executes the FOR to NEXT statement repeatedly until a specified value is exceeded.	×	Command Statements
G				
37	GOSUB to RETURN	Jumps to a subroutine with the label specified by a GOSUB statement, and executes that subroutine.	×	Command Statements
38	GOTO	Unconditionally jumps to the line specified by a label.	×	Command Statements
Н				
39	HALT	Stops the program and performs a reset.	×	Command Statements
40	HALTALL	Stops and resets all programs.	×	Command Statements
41	HAND	Defines the hand of a specified robot.	0	Command Statements
42	HOLD	Temporarily stops the program.	×	Command Statements
43	HOLDALL	Temporarily stops all programs.	×	Command Statements
ı				
44	IF	Allows control flow to branch according to conditions.	×	Command Statements
45	INPUT	Assigns a value to a variable specified from the programming box.	0	Command Statements
46	INT	Acquires an integer for a specified value by truncating all decimal fractions.	-	Functions
J				
47	JTOXY	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (→XYTOJ)	-	Functions
L			,	
48	LEFT\$	Extracts a character string comprising a specified number of digits from the left end of a specified character string.	-	Functions
49	LEFTY	Sets the hand system of a specified robot to "Left."	0	Command Statements
50	LEN	Acquires the length (number of bytes) of a specified character string.	-	Functions
51	LET	Executes a specified assignment statement.	0	Command Statements
52	LO	Outputs a specified value to the LO port to enable/disable axis movement.	0	Command Statements
53	LOCx	Specifies/acquires point data for a specified axis or shift data for a specified element.	-	Command Statements/ Functions
54	LSHIFT	Shifts a value to the left by the specified number of bits. (↔RSHIFT)	-	Functions
M				
55	MCHREF	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.	-	Functions
56	MID\$	Extracts a character string of a desired length from a specified character string.	-	Functions
57	MO	Outputs a specified value to the MO port.	0	Command Statements
58	MOTOR	Controls the motor power status.	0	Command Statements
59	MOVE	Performs absolute movement of all axes of a specified robot.	0	Command Statements

No.	Command	Function	Online	Туре
60	MOVEI	Performs relative movement of all axes of a specified robot.	0	Command Statements
0				
61	OFFLINE	Sets a specified communication port to the "offline" mode.	0	Command Statements
62	ON ERROR GOTO	If an error occurs during program execution, this command allows the program to jump to the error processing routine specified by the label without stopping the program, or it stops the program and displays the error message.	×	Command Statements
63	ON to GOSUB	Jumps to a subroutine with labels specified by a GOSUB statement in accordance with the conditions, and executes that subroutine.	×	Command Statements
64	ON to GOTO	Jumps to label-specified lines in accordance with the conditions.	×	Command Statements
65	ONLINE	Sets the specified communication port to the "online" mode.	0	Command Statements
66	ORD	Acquires the character code of the first character in a specified character string.	-	Functions
67	ORGORD	Specifies/acquires the axis sequence parameter for performing return-to-origin and an absolute search operation in a specified robot.	0	Command Statements/ Functions
68	ORIGIN	Performs a return-to-origin.	0	Command Statements
69	OUT	Turns ON the bits of the specified output ports and the command statement ends.	×	Command Statements
70	OUTPOS	Specifies/acquires the OUT enable position parameter of a specified robot.	0	Command Statements/ Functions
P				
71	PDEF	Defines the pallet used to execute pallet movement commands.	0	Command Statements
72	PMOVE	Executes the pallet movement command of a specified robot.	0	Command Statements
73	Pn	Defines points within a program.		Command Statements
74	PPNT	Creates point data specified by a pallet definition number and pallet position number.	-	Functions
75	PRINT	Displays a character string at the programming box screen.	0	Command Statements
76	PSHFRC	Specifies/acquires the pushing thrust parameter.	0	Command Statements/ Functions
77	PSHJGSP	Specifies/acquires the pushing check speed threshold parameter.	0	Command Statements/ Functions
78	PSHMTD	Specifies/acquires the pushing method parameter.	0	Command Statements/ Functions
79	PSHRSLT	Acquires the status at the end of the PUSH statement.	-	Functions
80	PSHSPD	Specifies/acquires the pushing movement speed parameter.	0	Functions
81	PSHTIME	Specifies/acquires the pushing time parameter.	0	Functions
82	PUSH	Executes a pushing operation in the axis unit.	0	Command Statements
R				
83	RADDEG	Converts a specified value to degrees. (↔DEGRAD)	-	Functions
84	REM	Expresses a comment statement.	×	Command Statements
85	RESET	Turns the bit of a specified output port OFF.	0	Command Statements
86	RESTART	Restarts another task during a temporary stop.	0	Command Statements
87	RESUME	Resumes program execution after error recovery processing.	×	Command Statements
88	RETURN	Returns the processing branching with GOSUB to the next line of GOSUB.	×	Command Statements
89	RIGHT\$	Extracts a character string comprising a specified number of digits from the right end of a specified character string.	-	Functions
90	RIGHTY	Sets the hand system of a specified robot to "Right."	0	Command Statements
91	RSHIFT	Shifts a value to the right by the specified number of bits. (→LSHIFT)	-	Functions

No.	Command	Function	Online	Туре
S				
92	SELECT CASE to END SELECT	Allows control flow to branch according to conditions.	×	Command Statements
93	SEND	Sends a file.	0	Command Statements
94	SERVO	Controls the servo ON/OFF of a specified axis or all axes of a specified robot.	0	Command Statements
95	SET	Turns the bit at the specified output port ON.	Δ	Command Statements
96	SHARED	Enables reference with a sub-procedure without transferring a variable.	×	Command Statements
97	SHIFT	Sets the shift coordinate for a specified robot by using the shift data specified by a shift variable.	0	Command Statements
98	SIN	Acquires the sine value for a specified value.	-	Functions
99	Sn	Defines the shift coordinates within the program.	0	Command Statements
100	SO	Outputs a specified value to the SO port.	0	Command Statements
101	SPEED	Changes the program movement speed of a specified robot.	0	Command Statements
102	SQR	Acquires the square root of a specified value.	-	Functions
103	START	Specifies the task number and priority ranking of a specified program, and starts that program.	0	Command Statements
104	STR\$	Converts a specified value to a character string (↔VAL)	-	Functions
105	SUB to END SUB	Defines a sub-procedure.	×	Command Statements
106	SUSPEND	Temporarily stops another task which is being executed.	×	Command Statements
107	SWI	Switches the program being executed, then begins execution from the first line.	×	Command Statements
T				
108	TAN	Acquires the tangent value for a specified value.	-	Functions
109	TCOUNTER	Outputs count-up values at 10ms intervals starting from the point when the TCOUNTER variable is reset.	-	Functions
110	TIME\$	Acquires the current time as an "hh:mm:ss" format character string.	-	Functions
111	TIMER	Acquires the current time in seconds, counting from 12:00 midnight.	-	Functions
112	ТО	Outputs a specified value to the TO port.	0	Command Statements
113	TOLE	Specifies/acquires the tolerance parameter of a specified robot.	0	Command Statements/ Functions
114	TORQUE	Specifies/acquires the maximum torque command value which can be set for a specified axis of a specified robot.	0	Command Statements/ Functions
V				
115	VAL	Converts the numeric value of a specified character string to an actual numeric value. (↔STR\$)	-	Functions
W				
116	WAIT	Waits until the conditions of the DI/DO conditional expression are met (with time-out).	×	Command Statements
117	WAIT ARM	Waits until the axis operation of a specified robot is completed.	×	Command Statements
118	WEIGHT	Specifies/acquires the tip weight parameter of a specified robot.	0	Command Statements/ Functions
119	WEND	Terminates the command block of the WHILE statement.	×	Command Statements
120	WHERE	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).	-	Functions
121	WHILE to WEND	Controls repeated operations.	×	Command Statements
122	WHRXY	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).	-	Functions
X				
123	XYTOJ	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (←JTOXY).	-	Functions

# Program commands

# General commands

No.	Command	Function	Online	Туре
25	DIM	Declares the array variable name and the number of elements.	×	Command Statements
51	LET	Executes a specified assignment statement.	0	Command Statements
84	REM	Expresses a comment statement.	×	Command Statements

## Arithmetic commands

No.	Command	Function	Online	Туре
1	ABS	Acquires the absolute value of a specified value.	-	Command Statements
9	ATN	Acquires the arctangent of the specified value.	_	Functions
9	ATN2	Acquires the arctangent of the specified X-Y coordinates.	_	Functions
15	cos	Acquires the cosine value of a specified value.	_	Functions
22	DEGRAD	Converts a specified value to radians (↔RADDEG).	-	Functions
26	DIST	Acquires the distance between 2 specified points.	-	Functions
46	INT	Acquires an integer for a specified value by truncating all decimal fractions.	-	Functions
54	LSHIFT	Shifts a value to the left by the specified number of bits. (↔RSHIFT)	-	Functions
83	RADDEG	Converts a specified value to degrees. (↔DEGRAD)	-	Functions
91	RSHIFT	Shifts a value to the right by the specified number of bits. (↔LSHIFT)	-	Functions
98	SIN	Acquires the sine value for a specified value.	-	Functions
102	SQR	Acquires the square root of a specified value.	-	Functions
108	TAN	Acquires the tangent value for a specified value.	-	Functions

#### Date / time

No.	Command	Function	Online	Туре
19	DATE \$	Acquires the date as a "yy/mm/dd" format character string.	-	Functions
109	TCOUNTER	Outputs count-up values at 10ms intervals starting from the point when the TCOUNTER variable is reset.	-	Functions
110	TIME \$	Acquires the current time as an "hh:mm:ss" format character string.	-	Functions
111	TIMER	Acquires the current time in seconds, counting from 12:00 midnight.	-	Functions

# Character string operation

No.	Command	Function	Online	Туре
14	CHR\$	Acquires a character with the specified character code.	-	Functions
48	LEFT \$	Extracts a character string comprising a specified number of digits from the left end of a specified character string.	-	Functions
50	LEN	Acquires the length (number of bytes) of a specified character string.	-	Functions
56	MID \$	Extracts a character string of a desired length from a specified character string.	-	Functions
66	ORD	Acquires the character code of the first character in a specified character string.	-	Functions
89	RIGHT \$	Extracts a character string comprising a specified number of digits from the right end of a specified character string.	-	Functions
104	STR\$	Converts a specified value to a character string (↔VAL)	-	Functions
115	VAL	Converts the numeric value of a specified character string to an actual numeric value. (←STR\$)	-	Functions

# Point, coordinates, shift coordinates

No.	Command	Function	Online	Туре
12	CHANGE	Switches the hand of a specified robot.	0	Command Statements
41	HAND	Defines the hand of a specified robot.	0	Command Statements
47	JTOXY	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (↔XYTOJ)	-	Functions
49	LEFTY	Sets the hand system of a specified robot to "Left."	0	Command Statements
53	LOCx	Specifies/acquires point data for a specified axis or shift data for a specified element.	-	Command Statements/ Functions
73	Pn	Defines points within a program.	0	Command Statements
74	PPNT	Creates point data specified by a pallet definition number and pallet position number.	-	Functions
90	RIGHTY	Sets the hand system of a specified robot to "Right."	0	Command Statements
99	Sn	Defines the shift coordinates in the program.	0	Command Statements
97	SHIFT	Sets the shift coordinate for a specified robot by using the shift data specified by a shift variable.	0	Command Statements
123	XYTOJ	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (←JTOXY).	-	Functions

# Branching commands

No.	Command	Function	Online	Туре
33	EXIT FOR	Terminates the FOR to NEXT statement loop.	×	Command Statements
36	FOR to NEXT	Controls repetitive operations. Executes the FOR to NEXT statement repeatedly until a specified value is exceeded.	×	Command Statements
37	GOSUB to RETURN	Jumps to a subroutine with the label specified by a GOSUB statement, and executes that subroutine.	×	Command Statements
38	GOTO	Unconditionally jumps to the line specified by a label.	×	Command Statements
44	IF	Allows control flow to branch according to conditions.	×	Command Statements
63	ON to GOSUB	Jumps to a subroutine with labels specified by a GOSUB statement in accordance with the conditions, and executes that subroutine.	×	Command Statements
64	ON to GOTO	Jumps to label-specified lines in accordance with the conditions.	×	Command Statements
92	SELECT CASE to END SELECT	Allows control flow to branch according to conditions.	×	Command Statements
121	WHILE to WEND	Controls repeated operations.	×	Command Statements

# Error control

No.	Command	Function	Online	Туре
62	ON ERROR GOTO	If an error occurs during program execution, this command allows the program to jump to the error processing routine specified by the label without stopping the program, or it stops the program and displays the error message.	×	Command Statements
87	RESUME	Resumes program execution after error recovery processing.	×	Command Statements
32	ERL	Gives the line No. where an error occurred.	-	Functions
32	ERR	Gives the error code number of an error which has occurred.	-	Functions

# Program & task control

# Program control

No.	Command	Function	Online	Туре
11	CALL	Calls a sub-procedure.	×	Command Statements
39	HALT	Stops the program and performs a reset.	×	Command Statements
40	HALTALL	Stops all programs, resets task 1, and terminates all other tasks.	×	Command Statements
42	HOLD	Temporarily stops the program.	×	Command Statements
43	HOLDALL	Temporarily stops all programs.	×	Command Statements
107	SWI	Switches the program being executed, performs compiling, then begins execution from the first line.	×	Command Statements

### Task control

No.	Command	Function	Online	Туре
13	CHGPRI	Changes the priority ranking of a specified task.	-	Command Statements
18	CUT	Terminates a task currently being executed or temporarily stopped.	0	Command Statements
35	EXIT TASK	Terminates its own task which is in progress.	×	Command Statements
82	PUSH	Executes a pushing operation in the axis unit.	0	Command Statements
86	RESTART	Restarts another task during a temporary stop.	0	Command Statements
103	START	Specifies the task number and priority ranking of a specified task, and starts that task.	0	Command Statements
106	SUSPEND	Temporarily stops another task which is being executed.	×	Command Statements

# Robot control

# Robot operations

No.	Command	Function	Online	Туре
12	CHANGE	Switches the hand of a specified robot.	0	Command Statements
28	DRIVE	Moves a specified axis of a specified robot to an absolute position.	0	Command Statements
29	DRIVEI	Moves a specified axis of a specified robot to a relative position.	0	Command Statements
41	HAND	Defines the hand of a specified robot.	0	Command Statements
49	LEFTY	Sets the hand system of a specified robot to "Left."	0	Command Statements
58	MOTOR	Controls the motor power status.	0	Command Statements
59	MOVE	Performs absolute movement of all axes of a specified robot.	0	Command Statements
60	MOVEI	Performs relative movement of all axes of a specified robot.	0	Command Statements
68	ORIGIN	Performs a return-to-origin.		Command Statements
72	PMOVE	Executes the pallet movement command of a specified robot.	0	Command Statements
90	RIGHTY	Sets the hand system of a specified robot to "Right."	0	Command Statements
94	SERVO	Controls the servo ON/OFF of a specified axis or all axes of a specified robot.	0	Command Statements

# Status acquisition

No.	Command	Function	Online	Туре
2	ABSRPOS	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)	-	Command Statements/ Functions
5	ARMCND	Acquires the current arm status of a specified robot.	-	Functions
6	ARMSEL	Acquires the current "hand system" setting of a specified robot.	-	Functions
7	ARMTYP	Acquires the "hand system" setting of a specified robot.	-	Functions
16	CURTQST	Acquires the current torque against the rated torque of a specified axis.	-	Functions
55	MCHREF	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.	_	Functions
79	PSHRSLT	Acquires the status at the end of the PUSH statement.	-	Functions
80	PSHSPD	Specifies/acquires the pushing movement speed parameter.	0	Command Statements/ Functions
81	PSHTIME	Specifies/acquires the pushing time parameter.	0	Command Statements/ Functions
117	WAIT ARM	Waits until the axis operation of a specified robot is completed.	×	Command Statements
120	WHERE	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).	-	Functions
122	WHRXY	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).	-	Functions

# Status change

No.	Command	Function	Online	Туре
3	ACCEL	Specifies/acquires the acceleration coefficient parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP1	Specifies/acquires the arch position 1 parameter of a specified robot.	0	Command Statements/ Functions
4	ARCHP2	Specifies/acquires the arch position 2 parameter of a specified robot.	0	Command Statements/ Functions

No.	Command	Function	Online	Туре
8	ASPEED	Specifies/acquires the AUTO movement speed of a specified robot.	0	Command Statements/ Functions
10	AXWGHT	Specifies/acquires the axis tip weight parameter of a specified robot.	0	Command Statements/ Functions
20	DECEL	Specifies/acquires the deceleration rate parameter of a specified robot.	0	Command Statements/ Functions
67	ORGORD	Specifies/acquires the axis sequence parameter for performing return-to-origin and an absolute search operation in a specified robot.	0	Command Statements/ Functions
70	OUTPOS	Specifies/acquires the OUT enable position parameter of a specified robot.	0	Command Statements/ Functions
71	PDEF	Defines the pallet used to execute pallet movement commands.	0	Command Statements
76	PSHFRC	Specifies/acquires the pushing thrust parameter.	0	Command Statements/ Functions
77	PSHJGSP	Specifies/acquires the pushing check speed threshold parameter.	0	Command Statements/ Functions
78	PSHMTD	Specifies/acquires the pushing method parameter.	0	Command Statements/ Functions
101	SPEED	Changes the program movement speed of a specified robot.	0	Command Statements
113	TOLE	Specifies/acquires the tolerance parameter of a specified robot.	0	Command Statements/ Functions
118	WEIGHT	Specifies/acquires the tip weight parameter of a specified robot.	0	Command Statements/ Functions

### Input/output & communication control

#### Input/output control

No.	Command	Function	Online	Туре
23	DELAY	Waits for the specified period (units: ms).	×	Command Statements
27	DO	Outputs a specified value to the DO port.	0	Command Statements
52	LO	Outputs a specified value to the LO port to enable/disable axis movement.	0	Command Statements
57	МО	Outputs a specified value to the MO port.	0	Command Statements
69	OUT	Turns ON the bits of the specified output ports and the command statement ends.	×	Command Statements
85	RESET	Turns the bit of a specified output port OFF.	0	Command Statements
95	SET	Turns the bit at the specified output port ON.	Δ	Command Statements
100	SO	Outputs a specified value to the SO port.	0	Command Statements
112	ТО	Outputs a specified value to the TO port.	0	Command Statements
116	WAIT	Waits until the conditions of the DI/DO conditional expression are met (with time-out).	×	Command Statements

#### Communication control

No.	Command	Function		Туре
65	ONLINE	Sets the specified communication port to the "online" mode.	0	Command Statements
61	OFFLINE	Sets a specified communication port to the "offline" mode.	0	Command Statements
93	SEND	Sends a file.	0	Command Statements

## Functions: in alphabetic order

No.	Function	Туре	Function
Α			
1	ABS	Arithmetic function	Acquires the absolute value of a specified value.
2	ABSRPOS	Arithmetic function	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)
3	ACCEL	Arithmetic function	Acquires the acceleration coefficient parameter of a specified robot.
4	ARCHP1	Arithmetic function	Acquires the arch position 1 parameter of a specified robot.
4	ARCHP2	Arithmetic function	Acquires the arch position 2 parameter of a specified robot.
5	ARMCND	Arithmetic function	Acquires the current arm status of a specified robot.
6	ARMSEL	Arithmetic function	Acquires the current "hand system" setting of a specified robot.
7	ARMTYP	Arithmetic function	Acquires the "hand system" setting of a specified robot.
8	ASPEED	Arithmetic function	Sets the automatic movement speed.
9	ATN	Arithmetic function	Acquires the arctangent of the specified value.
9	ATN2	Arithmetic function	Acquires the arctangent of the specified X-Y coordinates.
10	AXWGHT	Arithmetic function	Acquires the axis tip weight parameter of a specified robot.
С			
14	CHR\$	Character string function	Acquires a character with the specified character code.
15	cos	Arithmetic function	Acquires the cosine value of a specified value.
16	CURTQST	Arithmetic function	Acquires the current torque against the rated torque of a specified axis.
17	CURTRQ	Arithmetic function	Acquires the current torque value of the specified axis of a specified robot.
D			
19	DATE\$	Character string function	Acquires the date as a "yy/mm/dd" format character string.
20	DECEL	Arithmetic function	Acquires the deceleration rate parameter of a specified robot.
22	DEGRAD	Arithmetic function	Converts a specified value to radians (↔RADDEG).
26	DIST	Arithmetic function	Acquires the distance between 2 specified points.
E			
32	ERL	Arithmetic function	Gives the line No. where an error occurred.
32	ERR	Arithmetic function	Gives the error code number of an error which has occurred.
ı			
46	INT	Arithmetic function	Acquires an integer for a specified value by truncating all decimal fractions.
J		,	
47	JTOXY	Point function	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (↔XYTOJ)
L	•	•	
48	LEFT\$	Character string function	Extracts a character string comprising a specified number of digits from the left end of a specified character string.
50	LEN	Arithmetic function	Acquires the length (number of bytes) of a specified character string.
53	LOCx	Point function	Specifies/acquires point data for a specified axis or shift data for a specified element.
54	LSHIFT	Arithmetic function	Shifts a value to the left by the specified number of bits. (↔RSHIFT)

No.	Function	Туре	Function
M			
55	MCHREF	Arithmetic function	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.
56	MID\$	Character string function	Extracts a character string of a desired length from a specified character string.
0			
66	ORD	Arithmetic function	Acquires the character code of the first character in a specified character string.
67	ORGORD	Arithmetic function	Acquires the axis sequence parameter for performing return-to- origin and an absolute search operation of a specified robot.
70	OUTPOS	Arithmetic function	Acquires the OUT enable position parameter of a specified robot.
P			
74	PPNT	Point function	Creates point data specified by a pallet definition number and pallet position number.
76	PSHFRC	Arithmetic function	Specifies/acquires a pushing thrust parameter.
77	PSHJGSP	Arithmetic function	Specifies/acquires a pushing detection speed threshold parameter.
78	PSHMTD	Arithmetic function	Specifies/acquires a pushing type parameter.
79	PSHRSLT	Arithmetic function	Acquires the status when PUSH statement ends.
80	PSHSPD	Arithmetic function	Specifies/acquires the pushing movement speed parameter.
81	PSHTIME	Arithmetic function	Acquires the status at the end of the PUSH statement.
R			
83	RADDEG	Arithmetic function	Converts a specified value to degrees. (↔DEGRAD)
89	RIGHT\$	Character string function	Extracts a character string comprising a specified number of digits from the right end of a specified character string.
91	RSHIFT	Arithmetic function	Shifts a value to the right by the specified number of bits. $(\leftrightarrow \!\! LSHIFT)$
S			
98	SIN	Arithmetic function	Acquires the sine value for a specified value.
102	SQR	Arithmetic function	Acquires the square root of a specified value.
104	STR\$	Character string function	Converts a specified value to a character string (↔VAL)
T			
108	TAN	Arithmetic function	Acquires the tangent value for a specified value.
109	TCOUNTER	Arithmetic function	Outputs count-up values at 10ms intervals starting from the point when the TCOUNTER variable is reset.
110	TIME\$	Character string function	Acquires the current time as an "hh:mm:ss" format character string.
111	TIMER	Arithmetic function	Acquires the current time in seconds, counting from 12:00 midnight.
113	TOLE	Arithmetic function	Acquires the tolerance parameter of a specified robot.
114	TORQUE	Arithmetic function	Acquires the maximum torque command value which can be set for a specified axis of a specified robot.
٧			
115	VAL	Arithmetic function	Converts the numeric value of a specified character string to an actual numeric value. (←STR\$)
W			
118	WEIGHT	Arithmetic function	Acquires the tip weight parameter of a specified robot.
120	WHERE	Point function	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).

No.	Function	Туре	Function
122	WHRXY	Point function	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).
Х			
123	XYTOJ	Point function	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (↔JTOXY).

# 5 Functions: operation-specific

#### Point related functions

No.	Function name	Function
47	JTOXY	Converts joint coordinate data to Cartesian coordinate data of a specified robot. (↔XYTOJ)
53	LOCx	Acquires point data for a specified axis or shift data for a specified element.
74	PPNT	Creates point data specified by a pallet definition number and pallet position number.
120	WHERE	Reads out the current position of the arm of a specified robot in joint coordinates (pulse).
122	WHRXY	Reads out the current position of the arm of a specified robot as Cartesian coordinates (mm, degrees).
123	XYTOJ	Converts the point variable Cartesian coordinate data to the joint coordinate data of a specified robot. (←JTOXY).

#### Parameter related functions

No.	Function name	Function
2	ABSRPOS	Acquires the machine reference of the specified axis of a specified robot. (Valid only for axes where the return-to-origin method is set as "mark method".)
3	ACCEL	Acquires the acceleration coefficient parameter of a specified robot.
4	ARCHP1	Acquires the arch position 1 parameter of a specified robot.
4	ARCHP2	Acquires the arch position 2 parameter of a specified robot.
5	ARMCND	Acquires the current arm status of a specified robot.
6	ARMSEL	Acquires the current "hand system" setting of a specified robot.
7	ARMTYP	Acquires the "hand system" setting of a specified robot.
10	AXWGHT	Acquires the axis tip weight parameter of a specified robot.
16	CURTQST	Acquires the current torque against the rated torque of a specified axis.
17	CURTRQ	Acquires the current torque value of the specified axis of a specified robot.
20	DECEL	Acquires the deceleration rate parameter of a specified robot.
50	LEN	Acquires the length (number of bytes) of a specified character string.
55	MCHREF	Acquires the return-to-origin or absolute-search machine reference for a specified robot axis.
66	ORD	Acquires the character code of the first character in a specified character string.
67	ORGORD	Acquires the axis sequence parameter for performing return-to-origin and an absolute search operation of a specified robot.
70	OUTPOS	Acquires the OUT enable position parameter of a specified robot.
79	PSHRSLT	Acquires the status at the end of the PUSH statement.
113	TOLE	Acquires the tolerance parameter of a specified robot.
114	TORQUE	Acquires the maximum torque command value which can be set for a specified axis of a specified robot.
118	WEIGHT	Acquires the tip weight parameter of a specified robot.

No.	Function name	Function
1	ABS	Acquires the absolute value of a specified value.
9	ATN	Acquires the arctangent of the specified value.
9	ATN2	Acquires the arctangent of the specified X-Y coordinates.
15	cos	Acquires the cosine value of a specified value.
22	DEGRAD	Converts a specified value to radians (↔RADDEG).
26	DIST	Acquires the distance between 2 specified points.
46	INT	Acquires an integer for a specified value by truncating all decimal fractions.
54	LSHIFT	Shifts a value to the left by the specified number of bits. (↔RSHIFT)
83	RADDEG	Converts a specified value to degrees. (↔DEGRAD)
91	RSHIFT	Shifts a value to the right by the specified number of bits. ( $\leftrightarrow$ LSHIFT)
98	SIN	Acquires the sine value for a specified value.
102	SQR	Acquires the square root of a specified value.
108	TAN	Acquires the tangent value for a specified value.
115	VAL	Converts the numeric value of a specified character string to an actual numeric value. (↔STR\$)

#### Character string calculation related functions

No.	Function name	Function
14	CHR\$	Acquires a character with the specified character code.
19	DATE \$	Acquires the date as a "yy/mm/dd" format character string.
48	LEFT \$	Extracts a character string comprising a specified number of digits from the left end of a specified character string.
56	MID \$	Extracts a character string of a desired length from a specified character string.
89	RIGHT \$	Extracts a character string comprising a specified number of digits from the right end of a specified character string.
104	STR\$	Converts a specified value to a character string (↔VAL)

#### Parameter related functions

No.	Function name	Function
32	ERL	Gives the line No. where an error occurred.
32	ERR	Gives the error code number of an error which has occurred.
109	TCOUNTER	Outputs count-up values at 1ms intervals starting from the point when the TCOUNTER variable is reset.
110	TIME \$	Acquires the current time as an "hh:mm:ss" format character string.
111	TIMER	Acquires the current time in seconds, counting from 12:00 midnight.

# Index

## Index

	Command list with a robot specified
	Command Statement Format
A	Comment
Absolute reset	Communication port
Acceleration coefficient	Constant file 8-28
Acceleration setting	Control codes
Acquiring return-to-origin status	Control multiple robots
Acquiring the access level	CONT setting
Acquiring the break point status	Coordinate plane setting
Acquiring the current positions	Copying point comments
Acquiring the current positions on pulse unit coordinates 10-18	Copying point data
Acquiring the current positions on XY coordinates 10-19	Copying point data
Acquiring the emergency stop status	D
Acquiring the mode status	D
Acquiring the remaining memory capacity	Data file 8-1
Acquiring the servo status	Data file types
Acquiring the shift status	Data format conversion
Acquiring the tasks in RUN status	Data readout processing
Acquiring the tasks in SUSPEND status	Data write processing
Acquiring the tasks operation status	Deceleration rate
Acquiring the tasks operation status	Deceleration setting
All file	Declares array variable
Arch motion setting	Define point
Arithmetic assignment statement	Defines functions which can be used by the user 7-36
-	•
Arm look output 7.93	DI/DO conditional expressions 4-6 DI file 8-31
Arm lock output	
Arm lock output variable	DO file
Array subscript	Dummy argument
Array variable file	Dynamic variables
Array variables	
Assignment statement	E
AUTO movement speed	FOF 61-
Axis tip weight	EOF file
	Erasing area check output setting
В	Erasing general-purpose Ethernet port
Bu 6	Erasing hand 10-32
Bit Settings3-17	Erasing point comments
	Erasing point data
C	Erasing point name
	Erasing shift
Cartesian coordinate format	Error code number 7-112
CASE 7-151	Error processing
Changing the MANUAL mode speed 10-12	Error recovery processing
Changing the program attribute	Ethernet port communication file
Character constants	Executes absolute movement of specified axes 7-43
Character string	
Comparison 4-4	
Connection 4-4	
Link	

Operations 4-4

Character string assignment statement 7-81
Circular interpolation 7-94

F	Moves the specified robot axes in a relative manner 7-49
	Multi-task 6-1
Functions: in alphabetic order7-11, 11-12	Multitask 5-1
Functions: operation-specific7-13, 11-14	
6	N
G	Numeric constants 2-1
Global variable8-25	Transition constants
Global variables	0
	9
Н	Online Command List
	Online commands
Hand	Acquiring the value of a character string expression 10-23
Acquiring the status	Acquiring the value of a numerical expression 10-22
Define	Acquiring the value of a point expression 10-23
Definition file 8-15	Acquiring the value of a shift expression 10-23
Switche	Operation speed
Hand system flag 4-5, 7-97, 7-108, 7-127, 8-4, 8-18	OUT enable position 7-120
Hand system to "Right" 7-149	
	P
	Dellot
IF7-72	Pallet Define
Block IF statement	Definition file
Simple IF statement	Definition number
Initialize	Erasing
Communication port	Movement 7-123
memory area	Position number
Integer constants 2-1	Palletizing 9-4, 9-10
Internal output	Parallel input variable
Internal output variable	Parallel output variable 3-9
	Parallel port 7-39, 7-42
J	Parameter directory file
	Parameter file
Joint coordinate format	Performs absolute movement7-91, 7-106
	Pick and place9-12
L	Point assignment statement
	Point comment file 8-8
Label	Point data
LABEL Statement	Format
Left-hand system	Point data variable
Line number where error occurred	Point file 8-4
Local variable         7-165           Local variables         3-18	Port output setting 7-105
LO file	Priority of arithmetic operation
Logic operations 4-2	Program  Copy
Logio operations 4-2	Erase
M	Stop
M	Switche
MANUAL mode operation	Temporarily stop
MO file8-35	Program directory file8-22
Movement direction setting	Program execution wait
Movement speed 7-161	Program file 8-2

Program level 7-156	System prior to shipment 5-1
Program Names 1-2	System Variables
Program operations 10-6	
PTP movement of specified axis	Т
R	Task
	Condition wait 6-4
Read file	Definition 6-1
Ready queues 6-3	Deleting 6-6
Real constants	Directly terminate
Reference commands	Number 7-163
Relational operators	Priority order 6-1
Rename program name 10-34	Priority ranking7-28, 7-163
Reserved word list	Program example 6-8
Return-to-origin sequence 7-117	Restart 7-145
Robot Language Lists: Command list in alphabetic order 11-3	Restarting 6-5
Robot Language Lists: Function Specific	Scheduling 6-3
RS-232C 9-17, 9-18	Sharing the data 6-8
	Start 7-163
S	Starting 6-2
	Status and transition 6-2
SEQUENCE 1-2	Stopping 6-7
Sequence program	Suspending 6-5
Acquiring the execution status 10-17	Temporarily stop 7-167
Setting the execution flag 10-39	Terminate
SEQUENCE program 1-2	Task status
Serial double word input	NON EXISTEN 6-2
Serial double word output	READY 6-2
Serial input variable	RUN 6-2
Serial output variable	STOP 6-2
Serial port	SUSPEND 6-2
Serial port communication file	WAIT 6-2
Serial word input	Timer output variable
Serial word output	Tip weight 7-180
Servo	TO file
FREE 7-154	Tolerance
OFF 7-154	TO port
ON 7-154	Torque command value
Servo status 7-154	Type Conversions
Setting the sequence program execution flag	Type conversions
Shift assignment statement	- 11
Shift coordinate	U
Definition file	User program examples
Shift coordinate variable	Application 9-8
SI file	Basic operation
SO file	User Variables 3-2
SOW file	Using point numbers 9-2
Static variables 3-18	Using shift coordinates 9-3
STOPON condition setting	Using Shill Goordinates 9-3
STOPON conditions setting	· ·
Sub-procedure	V
Sub-routine	Valid range of dynamic array variables
Subroutine	Valid range of variables
Oubioutilie/-113	valid ratige of variables

Value Pass-Along & Reference Pass-Along	3-6
Variable file 8	-25
Variable Names	3-3
Variable Types	3-4
W	
WAIT status	
Write file 7-1	152
X	
XY setting	-46

#### Revision record

Manual version	Issue date	Description
Ver. 1.00	Apr. 2014	First edition
Ver. 1.10	Aug. 2014	Clerical errors were corrected, etc.

## **Programming Manual**

**RCX340** 

Aug. 2014 Ver. 1.10 This manual is based on Ver. 1.10 of Japanese manual.

#### YAMAHA MOTOR CO., LTD. IM Operations

All rights reserved. No part of this publication may be reproduced in any form without the permission of YAMAHA MOTOR CO., LTD. Information furnished by YAMAHA in this manual is believed to be reliable. However, no responsibility is assumed for possible inaccuracies or omissions. If you find any part unclear in this manual, please contact your distributor.

#### **IM Operations**

882 Soude, Nakaku, Hamamatsu, Shizuoka, 435-0054, Japan Tel. 81-53-460-6103 Fax. 81-53-460-6811

Robot manuals can be downloaded from our company website. Please use the following for more detailed information.

http://global.yamaha-motor.com/business/robot/

